



User Guide Volume 5

SUPPLY CHAIN MANAGEMENT

ENTERPRISE OPERATIONS PLAN
DISTRIBUTION REQUIREMENTS PLANNING
PRODUCT LINE PLAN
RESOURCE PLAN



78-0506A
Printed in the U.S.A.
August 2000

This document contains proprietary information that is protected by copyright. No part of this document may be reproduced, translated, or modified without the prior written consent of QAD Inc. The information contained in this document is subject to change without notice.

QAD Inc. provides this material as is and makes no warranty of any kind, expressed or implied, including, but not limited to, the implied warranties of merchantability and fitness for a particular purpose. QAD Inc. shall not be liable for errors contained herein or for incidental or consequential damages (including lost profits) in connection with the furnishing, performance, or use of this material whether based on warranty, contract, or other legal theory.

MFG/PRO is a registered trademark of QAD Inc. QAD, QAD eQ, and the QAD logo are trademarks of QAD Inc.

Designations used by other companies to distinguish their products are often claimed as trademarks. In this document, the product names appear in initial capital or all capital letters. Contact the appropriate companies for more information regarding trademarks and registration.

Copyright © 2000 by QAD Inc.
78-0506A

QAD Inc.
6450 Via Real
Carpinteria, California 93013
Phone (805) 684-6614
Fax (805) 684-1890
<http://www.qad.com>

Contents

ABOUT THIS GUIDE	1
Other MFG/PRO eB Documentation	2
Online Help	3
QAD Web Site	3
Conventions	4
 CHAPTER 1 INTRODUCTION TO SUPPLY CHAIN MANAGEMENT	 5
Enterprise Operations Plan (EOP)	6
Distribution Requirements Plan (DRP) and Other Planning Modules	6
Electronic Data Interchange (EDI)	7
 SECTION 1 ENTERPRISE OPERATIONS PLAN.....	 9
 CHAPTER 2 ABOUT OPERATIONS PLAN.....	 11
Introduction to Operations Planning	12
Operations Planning Example	15
Module Overview	18
 CHAPTER 3 REQUIRED IMPLEMENTATION.....	 21
Introduction	22
Setting Up Other Modules	22
Multiple Database	24

Manager Functions	24
General Ledger	24
Distribution Requirements Plan	25
Items/Sites	25
Resource Plan	26
Work Orders	26
Repetitive	26
Material Requirements Plan	27
Purchasing	27
Setting Up the Operations Plan Module	27
Review the General Ledger Calendar	27
Build Calendar Cross-References	28
Configure the Control File	29

CHAPTER 4 FAMILY DATA IMPLEMENTATION 31

Introduction	32
Defining Family Hierarchies	32
Setting Up Hierarchies	34
Copying Hierarchies	35
Changing Subfamily Relationships	36
Changing Subfamily Forecast Percentages	37
Establishing Target Inventory Levels	37
Setting Up Generic Coverage Factors	38
Setting Up Date-Specific Coverage Factors	39
Tracking Family Production Costs	40

CHAPTER 5 END-ITEM DATA IMPLEMENTATION 43

Introduction	44
Using Source Matrices	44
Setting Up Source Matrices	46
Using Line Allocations	47
Setting Up Line Allocations	47
Setting Target Inventory Levels	48
Loading Target Inventory Quantities	50

Setting Up Generic and Date-Specific Coverage Factors	50
Tracking Pallet Data	50
Setting Up Generic Pallet Information	50
Setting Up Item Pallet Information	51
CHAPTER 6 DATA COLLECTION.....	53
Introduction	54
Loading Data from MFG/PRO eB Databases	55
Loading Data from Non-MFG/PRO eB Databases	59
Loading Item-Site Data	59
Consolidating Loaded Data	60
Maintaining Loaded Data	61
Changing Sales Data	61
Reviewing Sales Data	62
Changing Inventory Data	63
Reviewing Inventory Data	64
Changing Production Data	64
Reviewing Production Data	65
CHAPTER 7 FAMILY-LEVEL PLANNING.....	67
Introduction	68
Calculating Family Plans	69
Maintaining Family Plans	70
Changing Family Plans	72
Reviewing Projected Profit	75
Exploding Family Plans	76
Reviewing Family Forecast Percentages	76
Exploding Family Plans	77
Rolling Up End-Item Changes	78
Running Family Plan Rollup	79
CHAPTER 8 END-ITEM PLANNING	81
Introduction	82
Calculating Operations Plans	83

Running Source Matrix Explosion	84
Maintaining Operations Plans	86
Reviewing Projected Resource Load	86
Changing Site Operations Plans	86
Reviewing Site Operations Plans	88
Changing Line Operations Plans	89
Reviewing Line Operations Plans	90
Changing Line Schedules	90
Reviewing Line Schedules	97
Reviewing Projected Inventory Coverage	97
Reviewing Site Utilization	97
Reviewing Production Labor Hours	97

CHAPTER 9 TRANSFER OF PRODUCTION DEMANDS. 99

Introduction	100
Exploding the Operations Plan into Orders	100
Running Operations Plan Explosion	101
Approving Orders to Other Modules	103
Running Operations Plan Approval	104
Running Operations Plan Batch Approval	106
Balancing Target Inventory Levels and MRP	106

CHAPTER 10 PERFORMANCE MEASUREMENT 109

CHAPTER 11 SIMULATION PLANNING 113

Introduction	114
Creating Simulation Plans	114
Maintaining Simulation Plans	116
Changing Site Simulation Plans	116
Changing Line Simulation Plans	117
Changing Simulation Line Schedules	118
Copying Simulation Plans to Active Plans	118

CHAPTER 12 SYSTEM ADMINISTRATION. 121

Introduction	122
Maintaining Static Data	122
Deleting Old Data	123
Recalculating Summary Records	124

CHAPTER 13 OPERATIONS PLAN EXAMPLES. 125

Family Plan Example	126
Global Consolidation	126
Family Plan Explosion	129
Family Plan Rollup	131
Operations Plan Example	133
Source Matrix Explosion	133

SECTION 2 DRP AND OTHER PLANNING MODULES. 139**CHAPTER 14 DISTRIBUTION REQUIREMENTS PLANNING. 141**

Introduction	142
Setting Up DRP	143
Pur/Mfg Code	143
Source Networks	144
Transportation Management	145
Master Scheduling Distribution Items	147
Executing DRP	148
DRP Modes	148
DRP and MRP	150
DRP Calculation and Processing	151
Pegging	151
Synchronized MRP/DRP Calculations	151
DRP Output	153
Intersite Requests	153
Distribution Orders	157

Purchase Orders and Sales Orders	163
DRP Action Messages	163

CHAPTER 15 PRODUCT LINE PLAN..... 167

Introduction	168
Creating Product Line Plans	168
Balancing Product Line Plans	170
Maintaining Product Line Plans	171

CHAPTER 16 RESOURCE PLAN..... 173

Introduction	174
Setting Up Resource Plans	174
Resource Codes	174
Resource Bills	175
Calculating Resource Plans	176
Evaluating Product Line Plans	176
Evaluating Manufacturing Schedules	177

INDEX..... 179

About This Guide

Other MFG/PRO eB Documentation 2

Online Help 3

QAD Web Site 3

Conventions 4

Routing Maintenance (Date Based)

Routing Code:	10-15000	NONAD(75) COOLING
Operation:	20	
Standard Operation		
Work Center	1030	INSPECTION, ALL SITES
Machine		
Description	INSPEC PER PROX-005	
Machines per Op	1	Milestone P
Overlap Units	1	
Queue Time	1.0	
Wait Time	0.0	
Setup Time	0.0	

Route by Production Route

This guide covers features related to Supply Chain Management in MFG/PRO eB.

Other MFG/PRO eB Documentation

- For an overview of new features and software updates, see the *Release Bulletin*.
- For software installation instructions, refer to the appropriate installation guide for your system.
- For instructions on navigating the MFG/PRO eB Windows and character environments, refer to *User Guide Volume 1: Introduction*. Navigation information for the Network User Interface (NetUI) is provided in the *Network User Interface Guide*.
- For information on using MFG/PRO eB, refer to the *User Guides*.
- For information on using features that let MFG/PRO eB work with external applications, see the *External Interface Guides*. For example, these guides describe the Warehousing application program interface (API) and Q/LinQ, the tool set for building and using tools that perform complex data exchange between MFG/PRO eB and external systems.
- For technical details, refer to *File Relationships* and *Database Definitions*.
- To view documents online in PDF format, see the *Documents on CD*. The CD-ROM media includes complete instructions for loading the documents on a Windows network server and making them accessible to client computers.

Note MFG/PRO eB installation guides are not included on *Documents on CD*. Printed copies are packaged with your software. Electronic copies of the latest versions are available on QAD's Web site.

Online Help

MFG/PRO eB has an extensive online help system. Help is available for most fields found on a screen. Procedure help is available for most programs that update the database. Most inquiries, reports, and browses do not have procedure help.

For information on using the help system in the different MFG/PRO eB environments, refer to *User Guide Volume 1: Introduction* and the *Network User Interface Guide*.

QAD Web Site

QAD's Web site provides a wide variety of information about the company and its products. You can access the Web site at:

<http://www.qad.com>

For MFG/PRO eB users with a QAD Web account, product documentation is available for viewing or downloading at:

<http://support.qad.com/documentation/>

To obtain a QAD Web account, go to:

<http://support.qad.com/>

Most user documentation is available in two formats:

- Portable document format (PDF). PDF files can be downloaded from the QAD Web site to your computer. You can view them with the free Adobe Acrobat Reader. A link for downloading this program is also available on the QAD Web site.
- HTML. You can view user documentation through your Web browser. The documents include search tools for easily locating topics of interest.

Features also include an online solution database to help MFG/PRO eB users answer questions about setting up and using the product. Additionally, the QAD Web site has information about training classes and other services that can help you learn about MFG/PRO eB.

Conventions

MFG/PRO eB is available in several interfaces: Windows, character, Web browser, and an interface for object-oriented programs. To standardize presentation, the documentation uses the following conventions:

- MFG/PRO eB screen captures show the Windows interface.
- References to keyboard commands are generic. For example, choose Go refers to F2 in the Windows interface and to F1 in the character interface. Throughout MFG/PRO eB, the PROGRESS status line at the bottom of the program window lists the main UI-specific keyboard commands used in that program.

For complete keyboard command summaries for each MFG/PRO eB interface, refer to the appropriate chapters of *User Guide Volume 1: Introduction* and the *Network User Interface Guide*.

This document uses the text or typographic conventions listed in the following table.

If you see:	It means:
monospaced text	A command or file name.
<i>italicized monospaced text</i>	Indicates a variable name for a value you enter as part of an operating system command. For example, <i>YourCDROMDir</i> .
indented command line	A long command that you enter as one line, although it appears in the text as two lines.
Note	Alerts the reader to exceptions or special conditions.
Important	Alerts the reader to critical information.
Warning	Used in situations where you can overwrite or corrupt data, unless you follow the instructions.

CHAPTER 1

Introduction to Supply Chain Management

Enterprise Operations Plan (EOP) 6

Distribution Requirements Plan (DRP) and Other Planning Modules 6


Electronic Data Interchange (EDI) 7

Routing Maintenance (Main Screen)

Routing Code:	10-15000	NONAD (75) CDR INC
Operation:	20	
Standard Operation		
Work Center	1030	INSPECTION, ALL SITES
Machine		
Description	INSPEC PER PROX-005	
Machines per Op	1	Milestone
Overlap Units	1	
Queue Time	1.0	
Wait Time	0.0	
Setup Time	0.0	

Route by Production Route

Fig. 1.1
Supply Chain
Management



Enterprise Operations Plan (EOP)

◆ See “Enterprise Operations Plan” on page 9.

Use the Enterprise Operations Plan (EOP) to balance supply and demand and reduce inventory levels across the enterprise by consolidating data from multiple sites and databases. EOP helps planners establish global inventory and production levels to satisfy sales forecasts while meeting objectives for profitability, productivity, inventory and lead time reductions, and customer service.

Distribution Requirements Plan (DRP) and Other Planning Modules

◆ See “DRP and Other Planning Modules” on page 139.

Use Distributions Requirements Plan (DRP) to manage supply and demand between sites. DRP calculates item requirements at a site and generates DRP orders at the designated supply sites. DRP orders provide intersite demand to MRP at the supply site. DRP shipments manage the transfer of material between sites with appropriate inventory accounting and visibility of orders in transit.

To plan by product line rather than individual item, use Product Line Plan. You can plan shipments, production, inventory, backlogs, and gross margins—all measured by overall sales and cost to ensure that the plan meets all the financial needs of the business.

Use the Resource Plan to check resource loads for both the product line plan and the master schedule. Resource checking is a necessary step for

validating the plans and master schedules before submitting them to MRP for detailed planning.

Electronic Data Interchange (EDI)


EDI is an important tool in supply chain management. You can use it to import and export standard business transactions between your company and its customers and suppliers using your E-mail system or modem.

MFG/PRO eB supports two kinds of EDI systems:

- Traditional EDI, which may require customization at the program level to ensure proper mapping of data elements.
- EDI ECommerce, which is globally deployable and provides EDI with reduced installation and support requirements. ECommerce processes international EDI document standards with most major third-party EDI communications or translation software—referred to collectively as EC subsystems—currently on the market.

EDI is closely related to customer and supplier scheduled orders. Many of the EDI programs supplied with MFG/PRO eB can be used to import and export the documents that form the basis of scheduled order processing. For this reason, even though EDI is a supply chain function, it is not discussed in this volume. Rather, it is grouped together in the discussion of Release Management.

▶ See *User Guide Volume 7: Release Management*.



SECTION 1

Enterprise Operations Plan

This section describes Enterprise Operations Plan:

<i>About Operations Plan</i>	11
<i>Required Implementation</i>	21
<i>Family Data Implementation</i>	31
<i>End-Item Data Implementation</i>	43
<i>Data Collection</i>	53
<i>Family-Level Planning</i>	67
<i>End-Item Planning</i>	81
<i>Transfer of Production Demands</i>	99
<i>Performance Measurement</i>	109
<i>Simulation Planning</i>	113
<i>System Administration</i>	121
<i>Operations Plan Examples</i>	125

About Operations Plan

This chapter introduces general concepts associated with operations planning. Then, it describes how the Enterprise Operations Plan module works and how you use it.

Introduction to Operations Planning **12**

Module Overview **18**

Routing Maintenance (Main Screen)

Routing Code:	10-15000	NONAD (75) CDR INC
Operation:	20	
Standard Operation		
Work Center	1030	INSPECTION, ALL SITE
Machine		
Description	INSPEC PER PROX-005	
Machines per Op	1	Milestone
Overlap Units	1	
Queue Time	1.0	
Wait Time	0.0	
Setup Time	0.0	

Route by Production Route


Introduction to Operations Planning

Large manufacturing companies normally have multiple sites. Each site handles at least one of the following activities.

- Sales
- Inventory storage and distribution
- Production

Example A company has five sites, as shown in Figure 2.1. The headquarters is in London. Four additional sites are in Geneva, Paris, Dublin, and Milan.

Fig. 2.1
Example of
Organization
Structure



Within a site, it is relatively easy to balance sales forecasts, inventory, and capacity. However, it is much harder to do this between sites. For example, Geneva often has inventory shortages, but Paris has surpluses. Also, Milan incurs high overtime costs even though Dublin has ample production capacity.

To control inventory levels and balance resources among sites, many manufacturers use supply chain management techniques such as:

- Setting up focused factories dedicated to specific manufacturing activities
- Consolidating purchasing across sites
- Defining target inventory coverage levels globally instead of by site

These techniques help. But without a central production planning tool, balancing supply and demand between sites in the supply chain is still a difficult task.

Operations planning is a strategic and tactical production planning tool designed to do exactly this. It is especially useful in high-volume, make-to-stock companies.

As a strategic tool, you can use operations planning to:

- Project long-term labor, equipment, and cash needs.
- Develop long-term material procurement plans for negotiations with major suppliers.

As a tactical tool, you can use operations planning to:

- Optimize target inventory and production levels throughout the enterprise.
- Identify variances between planned and actual performance.
- Develop schedules for sites and production lines.

Enterprise resource planning (ERP) is an information system for planning the company-wide resources needed to take, make, ship, and account for customer orders. In companies that use ERP, operations planning is the key link between long-term business planning and medium- to short-term planning and execution activities (Figure 2.2).




Fig. 2.2
Operations
Planning and ERP


Operations planning calculates target inventory levels that support company objectives for profitability, inventory and lead time reductions, customer service, and so on. It also calculates the corresponding

production demands. These demands eventually pass into production, purchasing, and material requirements planning (MRP).

The Enterprise Operations Plan module closely parallels the classic APICS model for sales and operations planning. However, it is superior in that it generates firm planned work orders that can replace master schedule orders. To prevent duplications, do not use the Forecast/Master Plan module for item-sites already included in operations planning.

Figure 2.3 summarizes how operations planning transforms data. Operations planning calculates target inventory levels based on upcoming sales forecasts. It also calculates production demands required for target inventory levels. For medium- to short-term planning, it nets these production demands against on-hand inventory balances.

Fig. 2.3
Operations Plan
Data Flow



Operations planning transforms production demands into firm planned work orders, repetitive schedules, or purchase requisitions. It also passes these demands into MRP/DRP, which calculates the component requirements.

Operations planning includes two major planning levels:

- Family-level planning. High-volume, make-to-stock companies frequently have a wide variety of similar items that differ only by size, color, packaging, or other minor characteristic. To simplify long-term business planning, these companies forecast and plan production by product family.
- End-item planning. In the medium to short term, companies forecast and plan production for end items.

Figure 2.4 summarizes the relationships between the two levels.





Fig. 2.4
Planning Levels

Operations Planning Example

Figure 2.5 shows the operations planning relationships between sites. In addition to marketing, London is the central site for operations planning. Each of the other four sites plans its own activities, then provides the local planning data to the London master scheduler.

See Figure 2.1 on page 12.

Fig. 2.5
Planning
Relationships



The London scheduler consolidates this data and calculates a weekly global operations plan for each product. This plan shows consolidated sales forecasts, target inventory levels, and production due.

London then distributes the global plan to all sites. The local site planners transform this plan into weekly production schedules.

In Table 2.1, London calculates a global operations plan. London, Geneva, and Paris generate sales forecasts. Milan and Dublin provide inventory required to satisfy these forecasts. London calculates global sales forecasts by consolidating its own forecasts with those from Geneva and Paris.

Table 2.1
Global Sales
Forecasts for
London

Week	Geneva Forecasts	Paris Forecasts	Global Forecasts
1	0	0	0
2	4,000	6,000	4,000 + 6,000 = 10,000
3	7,000	5,000	7,000 + 5,000 = 12,000
4	4,500	6,500	4,500 + 6,500 = 11,000
5	4,500	4,500	4,500 + 4,500 = 9,000
6	5,000	5,000	5,000 + 5,000 = 10,000
7	6,000	5,000	6,000 + 5,000 = 11,000
8	6,000	6,000	6,000 + 6,000 = 12,000
9	8,000	5,000	8,000 + 5,000 = 13,000

London calculates global target inventory levels to support the next two weeks of sales forecasts from London, Geneva, and Paris. Therefore, the target inventory level is the total global forecast for the next two weeks.

Week	Global Forecasts	Global Target Inventory Levels
1	0	$10,000 + 12,000 = 22,000$
2	10,000	$12,000 + 11,000 = 23,000$
3	12,000	$11,000 + 9,000 = 20,000$
4	11,000	$9,000 + 10,000 = 19,000$
5	9,000	$10,000 + 11,000 = 21,000$
6	10,000	$11,000 + 12,000 = 23,000$
7	11,000	$12,000 + 13,000 = 25,000$
8	12,000	$13,000 + 0 = 13,000$
9	13,000	0

Table 2.2

Global Forecasts and Target Inventory Levels for London

Production due is the consolidated production requirement, calculated with the following formula.

$$(Sales\ Forecast + Target\ Inventory) - Previous\ Week's\ Projected\ Quantity\ on\ Hand$$

For week 1, the projected quantity on hand is the ending inventory balance from the previous week (or 3,000, in this example). For weeks 2 to 9, projected quantity on hand equals the target inventory level for the previous week.

Wk	Forecasts	Target Inv	Prev QOH	Global Production Due
1	0	22,000	3,000	$(0 + 22,000) - 3,000 = 19,000$
2	10,000	23,000	22,000	$(10,000 + 23,000) - 22,000 = 11,000$
3	12,000	20,000	23,000	$(12,000 + 20,000) - 23,000 = 9,000$
4	11,000	19,000	20,000	$(11,000 + 19,000) - 20,000 = 10,000$
5	9,000	21,000	19,000	$(9,000 + 21,000) - 19,000 = 11,000$
6	10,000	23,000	21,000	$(10,000 + 23,000) - 21,000 = 12,000$
7	11,000	25,000	23,000	$(11,000 + 25,000) - 23,000 = 13,000$
8	12,000	13,000	25,000	$(12,000 + 13,000) - 25,000 = 0$
9	13,000	0	13,000	$(13,000 + 0) - 13,000 = 0$

Table 2.3

Production Calculations

London will use the operations plan to view the global picture of sales forecasts, target inventory, and production due for this item. Milan and Dublin will use it for site-level planning, scheduling, and manufacturing activities.

Table 2.4
Production
Calculations and
Projected
Quantities on Hand

Wk	Forecasts	Target Inventory	Production Due	Projected QOH
1	0	22,000	19,000	22,000
2	10,000	23,000	11,000	23,000
3	12,000	20,000	9,000	20,000
4	11,000	19,000	10,000	19,000
5	9,000	21,000	11,000	21,000
6	10,000	23,000	12,000	23,000
7	11,000	25,000	13,000	25,000
8	12,000	13,000	0	13,000
9	13,000	0	0	0

Module Overview

The Enterprise Operations Plan module has many useful features:

- Planning at family and/or end-item levels
- Demand consolidation from multiple sites and databases
- Production demands based on sales forecasts and inventory balances
- Target inventory levels in weeks of coverage, by effective date
- Intersite supply and demand relationships by effective date
- Production demands allocated to sites and lines by percentage
- Interface with resource planning
- Production line scheduling
- Production demand transfer to other modules
- Performance measurement reporting
- Simulation planning

Figure 2.6 summarizes the module work flow.




Fig. 2.6
Operations Plan
Work Flow

To generate any plan or performance measurement report, you must first collect item sales, inventory, and production data from company sites and databases. Operations planning activities do not affect the source transactions, only the collected data.

Family-level planning is optional but useful for limiting the number of items to be planned and for grouping items by brand name, target market, production process, and so on. To develop the family plan, you first generate site sales forecasts for each family item. Then, you consolidate these forecasts and calculate the family plan.

You verify the production quantities against known capacity constraints and modify them if necessary. To experiment with planning scenarios, create simulation plans. Then, you explode the plan to calculate the corresponding dependent end-item demand. This step passes the family plan production requirements into the end-item planning cycle.

Operations planning continues at the end-item level, and the processing steps roughly parallel those at the family level. To develop the end-item operations plan, you first load and consolidate sales forecast and inventory data for all company sites. Then, you use this data to calculate the operations plan for each end item.

You verify the production quantities against known capacity constraints and modify them if necessary. Again, you can create simulation plans. If you plan at the family level, you must also roll the changes back into the family plan.

Production demands from the operations plan affect subsequent manufacturing, planning, and purchasing activities. Once you are satisfied with the operations plan, run an explosion process to generate firm planned orders. These orders are similar to master schedule orders generated by the Forecast/Master Plan module. You can approve these orders as firm planned work orders, repetitive schedules, or purchase requisitions.

▶ See *User Guide Volume 3: Manufacturing* for information on MRP.

To ensure that MRP and sales forecast records remain synchronized, also run a balancing utility. Finally, run MRP/DRP to generate planned orders for component requirements.

At the end of the planning cycle, you measure actual vs planned sales, inventory, and production performance. To do this, load end-item data using the same data collection programs used to load plan data. If you plan at the family level, you also roll the actual end-item performance back up to the family level. Then, print and review performance reports.

CHAPTER 3

Required Implementation

This chapter describes setup activities required to use operations planning.

<i>Introduction</i>	<i>22</i>
<i>Setting Up Other Modules</i>	<i>22</i>
<i>Setting Up the Operations Plan Module</i>	<i>27</i>

param91.p 14.13.2 Routing Maintenance (Main Screen)

Routing Code:	10-15000	NONAUT (75) COOLING
Operation:	20	
Standard Operation		
Work Center	1030	INSPECTION, ALL SITES
Machine		
Description	INSPEC PER PROG-005	
Machines per Op	1	Milestone
Overlap Units	1	
Queue Time	1.0	
Wait Time	0.0	
Setup Time	0.0	

Revised by Production Support Group

Introduction

Regardless of how you plan to use the Enterprise Operations Plan module, it is important to set up data correctly not only in the module itself, but in all MFG/PRO eB modules that interact with the module.

Table 3.1
MFG/PRO eB
Modules and
Operations Plan

Module	Data
Multiple Database	Database connections
Manager Functions	Holidays, shop calendar, generalized codes, security
General Ledger	Financial calendar
Distribution Requirements Plan	Control file, network codes, source networks
Items/Sites	Sites and site security, product lines, unit of measure conversions, items
Resource Plan	Resource bills, item resource bills
Work Orders	Control file
Repetitive	Production lines, shift calendars
Material Requirements Plan	Control file
Purchasing	Control file

You also must perform some setup tasks within the Enterprise Operations Plan module.

Setting Up Other Modules

Figure 3.1 shows the modules that interact with operations planning calculations. Both the family plan and operations plan incorporate sales forecasts and inventory balances. The operations plan, in turn, can generate MRP and DRP requirements, work orders, repetitive schedules, and purchase requisitions.




Fig. 3.1
Plan Calculation
Inputs/Outputs

Figure 3.2 shows the modules that provide data to operations planning performance reports. Performance reports include quantities from completed work orders and repetitive schedules, purchase order receipts, sales order shipments, and inventory balances.




Fig. 3.2
Performance
Measurement
Inputs

You should implement most or all of the other required modules before implementing Operations Plan.

Implementation is also a good time to review your company’s coding schemes and other business practices to take advantage of capabilities offered by MFG/PRO eB.

Multiple Database

▶ See *User Guide Volume 9: Manager Functions*.

If you plan to import operations planning data from multiple databases, you must set up these connections.

In a multi-database environment, all databases that provide data for operations planning require consistent codes for items, sites, and so on. Inconsistencies can create problems transferring planning data between databases. If a database runs manufacturing software other than MFG/PRO eB, make sure that the codes from that database are duplicated in the MFG/PRO eB database used for operations planning.

Manager Functions

▶ See *User Guide Volume 9: Manager Functions* for information on calendars, generalized codes, and security.

Operations Plan uses the holiday calendar if Move Holiday Production Backward is Yes in the Operations Plan Control File (33.1.24). In this case, calculations reschedule production backward for non-production weeks.

Generalized codes for item type (pt_part_type) and item group (pt_group) are selection criteria in many operations planning reports and processes.

Set up security for most operations planning programs to prevent unauthorized changes to master data, family plans, and operations plans. This also reduces the possibility that someone will prematurely copy simulation plans over the live plans, approve operations plan orders, or delete records. You can set up security at the user password, menu, and field levels.

General Ledger

▶ See *User Guide Volume 4A: Financials*.

Operations planning inquiries and reports use the company financial calendar to display the family plan and operations plan in financial periods as well as calendar weeks. Before you implement Operations Plan, set up financial calendars to support the entire operations planning horizon.

Distribution Requirements Plan

In multisite environments, use the Distribution Requirements Plan module to link sales forecasts and their corresponding production requirements.

▶ See Chapter 14, “Distribution Requirements Planning,” on page 141.

Set the DRP Control File (12.13.24) to support combined MRP/DRP processing. That way, whenever you run MRP, the system also runs DRP, and vice versa. DRP uses the network and source network codes to distribute operations plan item requirements among company sites.

Items/Sites

Most operations planning records and activities are associated with specific company sites. Set up site security in the System Security menu (36.3).

▶ See *User Guide Volume 9: Manager Functions*.

All items used for operations planning are associated with a product line. Product line is a selection criteria in some operations planning reports and processes.

Set up unit of measure conversion factors whenever you plan sales, inventory, and production in different units of measure. For example, you may plan sales and inventory in cases, but production in tons. Similarly, you need conversion factors whenever you use different units of measure for family-level and end-item planning. You may plan in metric tons at the family level but use kilos at the end-item level.

Set up item and item-site records for all items included in operations planning calculations.

- End items are grouped for family-level planning under a family item number.
- The operations plan approval programs use the item-site Pur/Mfg code. Set it to blank or M for manufactured items, L for line manufactured items, P for purchased items, or F for family and subfamily items. For DRP items, set it to D in item-site records for marketing sites—sites that generate sales forecasts for the item.
- For DRP items, specify the network code.

- Operations planning uses the time fence. When you calculate or explode the operations plan, you can protect items from last-minute changes inside the time fence.
- For purchased items, operations planning uses inspection, safety, and purchasing lead times for production scheduling.
- For manufactured items, operations planning uses manufacturing and safety lead times for production scheduling.
- Operations planning target inventory calculations ignore safety stock quantities.

Resource Plan

▶ See Chapter 16, “Resource Plan,” on page 173.

A primary objective of operations planning is to verify projected production load from the family plan and operations plan against available capacity. Therefore, you must set up resource bill records for critical resources such as equipment and labor. Operations planning uses item resource bills to calculate projected load for individual items.

Work Orders

▶ See *User Guide Volume 3: Manufacturing*.

To process operations plan production requirements as work orders, implement the Work Orders module.

Repetitive

▶ See *User Guide Volume 3: Manufacturing*.

To process operations plan production requirements as repetitive schedules, implement the Repetitive module.

In the Enterprise Operations Plan module, you can allocate production requirements by percentage between multiple lines in a site. The production line record has an additional Primary Line field when you implement Operations Plan. This field identifies whether a line is an item’s sole production line. If your company currently uses Repetitive, during the conversion process, you must run Production Line Update (33.25.3) to update existing production line records before you can set up line allocation records in Operations Plan. Operations Plan also uses the line’s run crew size to project site labor hours.

Operations Plan uses line shift calendars to calculate the number of available production hours and utilization for each production line. If no shift calendar is available, it uses the shop calendar for the supply site.

Material Requirements Plan

If you use DRP, you can set the MRP Control File (23.24) to support combined MRP/DRP processing. That way, when you run MRP, the system also runs DRP, and vice versa.

▶ See *User Guide Volume 3: Manufacturing*.

Purchasing

To process operations plan production requirements as purchase requisitions, implement the Purchasing module.

▶ See *User Guide Volume 2: Distribution*.

Setting Up the Operations Plan Module

Programs used for Operations Plan system setup are located in the System Setup Menu (33.1). The system setup is mandatory for all installations.

- Review the GL calendar
- Build calendar cross-references
- Set up the Operations Plan Control File

Review the General Ledger Calendar

Before building calendar cross-references, review the general ledger calendar.


- Use GL Calendar Browse (33.1.1) to show calendar periods starting with a specific fiscal year.
- Use GL Calendar Report (33.1.2) to show calendar periods for a range of entities and fiscal years.

Note The system defines the first week of a new calendar year as the first Thursday in January, in accordance with ISO standards.

Build Calendar Cross-References

In the Enterprise Operations Plan module, you can plan production either in calendar weeks (Monday–Sunday) or in financial periods. Calendar Cross-Reference Build (33.1.4) creates records that link the calendar and the financial calendar.

Fig. 3.3
Calendar Cross-
Reference Build
(33.1.4)



Year/To. Enter a range of calendar years, starting with the current year.

Table 3.2 shows typical linkages created by the build process.

Table 3.2
Calendar Cross-
References

Shop Calendar Weeks		Fiscal Periods
001 January 1 – 7	=	001 January 1 – 31
002 January 8– 14	=	001 January 1 – 31
003 January 15 – 21	=	001 January 1 – 31
004 January 22– 28	=	001 January 1 – 31
005 January 29 – February 4	=	001 January 1 – 31
006 February 5 – 11	=	002 February 1 – 29

If a calendar week spans two financial periods, the build assigns the week to the period associated with the Monday date.

Example You run the build and you have a monthly financial calendar. Week 005 is January 29 – February 4, but the week is linked to period 1 because Monday, January 29 is still in period 1. The build does this because planning activities assign item quantities to the Monday of the week.

Use Calendar Cross-Reference Inquiry (33.1.5) to verify that cross-references between calendar weeks and general ledger periods now exist for all years in the planning horizon, including the current year. Before planning for a new year, verify that cross-references exist for that year. If they do not, build them.

Configure the Control File

The settings in Operations Plan Control File (33.1.24) affect family plan and operations plan calculations. You can reconfigure the control file at any time. Changes to control file settings affect only subsequent planning activities.




Fig. 3.4
Operations Plan
Control File
(33.1.24)

Use Operations Plan. Enter Yes to activate operations planning fields in other modules.

Maximum Weeks Coverage. Enter the maximum number of upcoming weeks (greater than zero but less than 99.99) the system should scan when netting sales forecasts against inventory balances. This setting affects the processing time of these calculations.

Move Holiday Production Backward. Enter Yes to prevent the system from scheduling production for non-production weeks. A non-production week is one that has no scheduled work days. Every day in the non-production week must be set up as a holiday in Holiday Maintenance (36.2.1).

Use Rounding. Enter Yes if family plan and operations plan calculations should round item quantities to whole numbers. Enter No if they should calculate decimal quantities.

CHAPTER 4

Family Data Implementation

Before you implement data for family-level operations planning, you must implement the standard MFG/PRO eB and Enterprise Operations Plan module data listed in Chapter 3.

Introduction 32

Defining Family Hierarchies 32

Establishing Target Inventory Levels 37

Tracking Family Production Costs 40

Routing Maintenance (Main Screen)

Routing Code:	10-15000	NONAUTOMATIC
Operation:	20	
Standard Operation:	1030	INSPECTION, ALL SITES
Work Center:		
Machine:	INSPEC	
Description:	INSPEC PER PROX-000	
Machines per Op:	1	
Overlap Units:	1	
Queue Time:	1.0	
Wait Time:	0.0	
Setup Time:	0.0	


Introduction

Companies typically do family-level operations planning in the long- to medium-term horizon, anywhere from six months to three years. They use it to:

- Project long-term labor, equipment, and financial commitments.
- Develop long-term material procurement plans for negotiations with strategic suppliers.

For family-level planning, MFG/PRO eB uses three sets of data elements, as shown in Figure 4.1. You can set them up in any order.

Fig. 4.1
Family Data
Implementation
Work Flow



Programs used for family data implementation are located in the Family Setup Menu (33.3) and in the Item Setup Menu (33.5).

Defining Family Hierarchies

For operations planning, the family hierarchy defines several things:

- Nature of demand relationships for a product family
- End items and subfamilies in the family, and the percentage of total family sales forecast contributed by each
- Marketing sites that generate sales forecasts

Family hierarchies resemble product structures. The hierarchy consists of a parent family item and one or more subfamilies. Subfamilies can be either lower-level hierarchies or end items. Subfamilies in the lowest level must be end items. Within a hierarchy, each subfamily contributes a percentage of the total sales forecast for the family item.

Example The Firenze brand is a top-level family with its marketing site in London. The Firenze family has two subfamilies, Rainbow flavor (30% of demand) and Strawberry flavor (70% of demand). Each subfamily is also a lower-level hierarchy with two end items, an 18-carton case and a 36-carton case.





Fig. 4.2
Family Hierarchies

You can set up flexible hierarchies that mirror your company's planning groups. For example, you can set up hierarchies by buyer/planner group, brand, flavor, color, distribution channel, sales region, production line, and so on. The same subfamily or end item can belong to multiple families. Marketing may plan items by geographic region or brand name, but production plans by similarity of manufacturing process.

Subfamily relationships and percentages usually vary by marketing site and planning year. Typically, you set up multiple sets of subfamily relationships for each family hierarchy. Figure 4.3 summarizes the setup work flow.

Fig. 4.3
Hierarchy Setup
Work Flow



Setting Up Hierarchies

To set up new hierarchies and to change forecast percentages for existing hierarchies, use Family Hierarchy Maintenance (33.3.1). When you set up hierarchies, the system checks for cyclical relationships to prevent you from accidentally assigning a subfamily to itself.

Set up a hierarchy for every family item. Start from the lowest level and work upward to the top family level. The subfamilies for the lowest level must be end items.

Fig. 4.4
Family Hierarchy
Maintenance
(33.3.1)

The screenshot shows the 'Family Hierarchy Maintenance' window. The title bar reads 'Family Hierarchy Maintenance'. Below the title bar is a menu bar with 'User Menu', 'Edit', 'Queue', 'Options', and 'Help'. A toolbar with various icons is located below the menu bar. The main data area contains the following fields and values:

- Family Item: 0110
- Ice Dream (Brand Name)
- Subfamily Item: 0210
- Site: PARIS
- Paris, France
- Effective Year: 1996
- Forecast Percent: 35.00%
- Remarks: Hierarchy Level 1

Family Item. Enter the family item number. This item must be set up previously in Item Master Maintenance with a Pur/Mfg code of F (family).

Subfamily Item. Enter the end-item or family-item number to assign to this level of the hierarchy.

Site. Enter the site code.

Effective Year. Enter the hierarchy year.

Forecast Percent. Enter the percentage of the total family sales forecast typically contributed by this subfamily. Family Plan Explosion (33.7.14) can use this percent to calculate dependent end-item production demands from family demands.

Remarks. Optionally enter a remark about the subfamily level. This remark prints on the Family Hierarchy Report (33.3.3).

Use three programs to review hierarchy data:

- Family Hierarchy Inquiry (33.3.2) displays subfamily levels in a family hierarchy by year, site, level, and item.
- Family Hierarchy Report (33.3.3) is similar, but you can select information for a range of items, sites, and years.
- Family Hierarchy Where-Used Inquiry (33.3.8) displays family items that include the specified subfamily.

Copying Hierarchies

To copy hierarchy records, use Family Hierarchy Copy (33.3.5). For every family item, you must set up subfamily relationships for all marketing sites and years in the planning horizon.

Year	Site	Level	Item	Description	Fcst Pct
1996	LONDON	1	0210	Vanilla Ice Cream	30.00%
1996	LONDON	1	0220	Chocolate Ice Cream	70.00%
1996	LONDON	.2	0421	Chocolate Ice Cream	25.00%
1996	LONDON	.2	0422	Chocolate Ice Cream	75.00%

Fig. 4.5
Family Hierarchy
Copy (33.3.5)

Source Family Item. Enter the family item number for the source subfamily.

Source Site. Enter the code for the source subfamily's marketing site.

Effective Year. Enter the effective year for the source subfamily relationship.

Target Family Item. Enter the family item number for the target subfamily.

Target Site. Enter the code for the target subfamily's marketing site.

Effective Year. Enter the hierarchy year for the target subfamily relationship.

Changing Subfamily Relationships

After you copy hierarchies, use Family Hierarchy Change (33.3.6) to add, delete, or replace subfamilies for individual marketing sites and years.

Note Regardless of how you change subfamilies, you must later adjust the forecast percentages for all other subfamilies at the affected level, in all hierarchy records you change.

Fig. 4.6
Family Hierarchy
Change (33.3.6)

Family Hierarchy Change

User Menu Edit Queue Options Help

Subfamily Item: 0220 ↑ Chocolate Ice Cream
 UM: TN Subfamily
 Site: PARIS To: PARIS
 Effective Year: 1996 To: 1996

Action: A
 A - Add new subfamily item
 D - Delete existing subfamily item
 R - Replace existing subfamily item
 with new subfamily item

New Subfamily Item: 0230 French Vanilla Subfamily
 UM: CS

Subfamily Item. Enter the number of an end item or family item for the subfamily level affected by the change.

Site/To. Enter a range of sites to be updated.

Effective Year/To. Enter a range of years to be updated.

Action. Enter the action you want to take with this family relationship:

- **Add.** The system adds it (along with its lower-level subfamilies, if any) to the same level of the hierarchy as the subfamily item you specify. It also copies the existing subfamily's forecast percent to the new subfamily.
- **Delete.** The system deletes the subfamily relationship with any higher- or lower-level hierarchies. However, it does not delete lower-level hierarchies previously linked to the subfamily.

- **Replace.** The system replaces only the subfamily item. It does not change lower-level subfamily relationships.

New Subfamily Item. Enter the number of the family item or end item to replace the specified subfamily item.

UM. The screen displays the inventory unit of measure from the item master record.

Changing Subfamily Forecast Percentages

Whenever you adjust subfamily relationships, you must also adjust forecast percentages for other subfamilies at the affected level. For each level, make sure the percentages add up to 100%.

The screenshot shows a software window titled "Family Hierarchy Maintenance". It has a menu bar with "User Menu", "Edit", "Queue", "Options", and "Help". Below the menu is a toolbar with several icons. The main area displays the following information:

- Family Item: 0110 Ice Dream (Brand Name)
- Subfamily Item: 0210
- Site: PARIS Paris, France
- Effective Year: 1996
- Forecast Percent: 35.00%
- Remarks: Hierarchy Level 1

Fig. 4.7
Family Hierarchy
Maintenance
(33.3.1)

Subfamily
Forecast
Percent

Establishing Target Inventory Levels

Operations planning calculates global target inventory levels to support an item's sales forecasts. In turn, it calculates production requirements based on target inventory levels.

If you do not specify otherwise, the system automatically sets each week's target inventory level to zero. When set this way, you cannot build up inventory for future demands. You also cannot anticipate inventory shortages or surpluses.

To establish target inventory levels, define global weeks-of-coverage factors for minimum, average, and maximum target inventory levels. This method requires more implementation effort. However, it does support inventory buildup for upcoming sales forecasts.

Table 4.1 illustrates how the system uses coverage factors on the family plan. In the example, the system uses an average cover factor of 2.0 to calculate the target inventory level.

Table 4.1
Weeks of Coverage
on Operations Plan

No.	Sales Forecast	Target Inventory	Production Due	Projected QOH	Coverage
1	0	500	500	500	2.0
2	300	700	500	700	2.0
3	200	500	0	500	1.0
4	500	0	0	0	0.0

When you change production due quantities on the plan, it uses the minimum (–) and maximum (+) factors to alert you to potential inventory shortages and surpluses relative to the average coverage level. This is illustrated in Table 4.2, which assumes a minimum coverage of 1.0 and a maximum of 3.0.

Table 4.2
Weeks of Coverage
on Operations
Plan—Production
Due Quantities
Changed

No.	Sales Forecast	Target Inventory	Production Due	Projected QOH	Coverage	
1	0	500	200	200	0.7	–
2	300	700	500	400	1.4	
3	200	500	0	200	0.4	–
4	500	0	0	–300	0.0	–

Note You can define coverage factors for either top-level family items or for end items. However, to prevent the system from inflating inventory, do not set up coverage factors for both levels or for intermediate subfamily levels.

Setting Up Generic Coverage Factors

Use Weeks of Coverage Maintenance (33.5.1) to set up an item's generic coverage factors. Coverage factors are global, not site-specific, and they must be positive whole numbers.

Weeks of Coverage Maintenance	
User Menu Edit Queue Options Help	
Item Number: 0110	
UM: TN	
Ice Dream (Brand Name)	
Top-Level Family	
Minimum Weeks of Coverage:	1.0
Average Weeks of Coverage:	2.0
Maximum Weeks of Coverage:	3.0

Fig. 4.8
Weeks of Coverage
Maintenance
(33.5.1)

Item Number. Enter the family item number.

UM. The screen displays the inventory unit of measure from the item master record.

Minimum Weeks of Coverage. Enter the minimum number of weeks of global inventory coverage required for this item. The system uses this factor to calculate and display projected inventory shortages.

Average Weeks of Coverage. Enter the number of weeks of upcoming sales forecasts that corresponds to your company's desired inventory coverage level for this item. Plan calculations use this factor to calculate target inventory levels.

Maximum Weeks of Coverage. Enter the maximum number of weeks of global inventory coverage required for this item. The system uses this factor to calculate and display projected inventory surpluses.

Use two programs to review weeks of coverage factor data:

- Weeks of Coverage Inquiry (33.5.2) displays coverage factors by item, purchase/manufacture code, and buyer/planner.
- Weeks of Coverage Report (33.5.3) is similar to the inquiry, but you can also select information for a range of items.

Setting Up Date-Specific Coverage Factors

To manage items with varying coverage levels, set up date-specific factors in Coverage by Date Maintenance (33.5.5). You must set up generic coverage factors before date-specific factors.

Fig. 4.9
Coverage by Date
Maintenance
(33.5.5)

See page 39.

This program is similar to Weeks of Coverage Maintenance (33.5.1) but has two additional fields.

Start. Enter the start date for using this record in operations planning. The default is the system date.

End. Enter the end date for using this record in operations planning, or leave it blank.

Use two programs to review date of coverage factor data:

- Coverage by Date Inquiry (33.5.6) displays coverage factors by item, and purchase/manufacture code.
- Coverage by Date Report (33.5.7) enables you to select information for a range of items and start/end dates.

Tracking Family Production Costs

You can record reference information on production costs for product families. However, Operations Plan does not use this information in family plan calculations.

You can maintain multiple sets of hourly production costs for each family item. Each set of costs is uniquely identified by the cost set code and the family item site. If your company uses the Cost Management module, you can set up family costs for a variety of cost sets.

Use Family Item Cost Maintenance (33.3.13) to set up family item production costs.

Family Item Cost Maintenance			
User Menu Edit Queue Options Help			
Family Item: 0510		Firenze (Brand Name)	
UM: TN		Top-Level Family	
Site: LONDON		London, England	
Cost Set Selection			
Cost Set: Standard		Cost Set Type: GL	Costing Method: STD
Family Item Cost Data			
Production Rate	500.00	Cost	50.00
Production Rate	0.00	Cost	0.00
Production Rate	0.00	Cost	0.00
Production Rate	0.00	Cost	0.00
Production Rate	0.00	Cost	0.00

Fig. 4.10
Family Item Cost
Maintenance
(33.3.13)

Family Item. Enter the family item number.

UM. The screen displays the inventory unit of measure from the item master record.

Site. Enter the site code.

Cost Set. Enter the cost set code.

Cost Set Type. The screen displays the cost set type for the cost set.

Costing Method. The screen displays the costing method for the cost set.

Production Rate. Enter the average hourly production rate for end items in this family. The production rate is the number of units of the family item that can normally be produced per hour on a production line.

Cost. Enter the average hourly production cost for end items in this family. The production cost is the normal hourly production cost for the specified number of units of the family item.

Use two programs to review family item cost data:

- Family Item Cost Inquiry (33.3.14) displays production rates and costs by family item, site, and cost set.
- Family Item Cost Report (33.3.15) enables you to select information for a range of items, sites, and cost sets.

CHAPTER 5

End-Item Data Implementation

Before you implement data for end-item operations planning, you must implement the standard MFG/PRO eB and Enterprise Operations Plan module data listed in Chapter 3.

<i>Introduction</i>	44
<i>Using Source Matrices</i>	44
<i>Using Line Allocations</i>	47
<i>Setting Target Inventory Levels</i>	48
<i>Tracking Pallet Data</i>	50

Routing Code: 10-15000
Operation: 20
Standard Operation: 1030
Work Center: Machine
Description: INSPEC PER PROX-000
Machines per Op: 1
Overlap Units: 1
Queue Time: 1.0
Wait Time: 0.0
Setup Time: 0.0
Check Master


Introduction

Companies typically do end-item operations planning in a short to medium-term time frame, usually less than six months. They use it to:

- Optimize target inventory and production levels throughout the enterprise.
- Develop production schedules for supply sites and production lines.
- Identify variances between planned and actual performance.

For end-item planning, MFG/PRO eB uses four sets of data elements, as shown in Figure 5.1. You can set them up in any order.

Fig. 5.1
End-Item Data
Implementation
Work Flow



Using Source Matrices

For operations planning, the item source matrix defines the nature of supply and demand relationships for end items. It identifies the marketing sites that generate sales forecasts. It also defines how the operations plan calculation distributes global production demands to supply sites.

▶ See “Source Networks” on page 144.

Item source matrices resemble single-level DRP source networks. The source matrix consists of one or more marketing sites. Each marketing site, in turn, has one or more supply sites. Each supply site has a percentage that specifies how much of the item’s global production demand it contributes.

Figure 5.2 shows a sample source matrix.




Fig. 5.2
Sample Source
Matrix

The source matrix for item 0711 has three marketing sites that generate sales forecasts—London, Geneva, and Paris. London has two supply sites—Dublin, which supplies 50% of London’s production demand, and Milan, which supplies 50%. Geneva and Paris each have one supply site, Milan, which supplies 100% of their production demands.

Note For better tracking of requirements between sites, multisite companies should use Operations Plan together with DRP. DRP generates intersite requests that identify the marketing sites that originated the demands.

▶ See “Intersite Requests” on page 153.

To include an item in the operations plan, you must set up a source matrix for it. The same site can be both a marketing site and a supply site (set supply percent to 100%).

If you use DRP, the operations planning source matrix relationships for marketing and supply sites must mirror the DRP source networks.

Setting Up Source Matrices

To set up source matrices, use Source Matrix Maintenance (33.5.13).

Fig. 5.3
Source Matrix
Maintenance
(33.5.13)

The screenshot shows a window titled "Source Matrix Maintenance" with a menu bar (User Menu, Edit, Queue, Options, Help) and a toolbar. The main area contains the following fields:

Item Number: 0711	Rainbow Ice Cream
Marketing Site: LONDON	London, England
Supply Site: DUBLIN	Dublin, Ireland
Start: 01/01/96	
End: 12/31/97	
Supply Percent: 50.0%	
Transport Code:	
Lead Time:	

Item Number. Enter the end-item number.

Marketing Site. Enter the code for the marketing site. A marketing site is any site that generates sales forecasts. Examples include sales offices and distribution centers. An item can have multiple marketing sites in its source matrix.

Supply Site. Enter the code for the supply site. A supply site is any site that provides inventory to a marketing site. For manufactured items, the factory is typically the supply site. For purchased items, the purchasing site is the supply site. In a source matrix, a marketing site can have multiple supply sites.

Start. Enter the start date for using this source matrix in operations planning. To use the source matrix to calculate this week's operations plan, you must set the start date to the previous Monday or earlier.

End. Enter the end date for using this record in operations planning, or leave it blank.

Supply Percent. Enter the percentage of the marketing site's production requirement provided by this supply site. If the marketing site and supply site are the same, enter 100.0%. The system does not verify that the percentages for a marketing site's supply sites total 100.0%.

Transport Code. Enter the transportation code (if any) for inventory the supply site provides to the marketing site. Record this if needed for reference.

Lead Time. Enter the transportation lead time (if any) for inventory the supply site provides to the marketing site. Record this if needed for reference.

Use two programs to view source matrix data:

- Source Matrix Inquiry (33.5.14) shows marketing and supply site relationships by item.
- Source Matrix Report (33.5.15) is similar, but you can specify ranges of items, sites, and effectivity dates.

Using Line Allocations

Within a supply site, items can be produced on one or more production lines. The line allocation defines how production is distributed between these lines. Figure 5.4 shows how the Milan supply site allocates 25% of its production demand to Line 1 and the remaining 75% to Line 2.




Fig. 5.4
Production Line
Allocations

Setting Up Line Allocations

To set up production line allocations, use Line Allocation Maintenance (33.5.17). Set up line allocations only for items produced on multiple production lines within a site. The line percentages must total 100%.

Fig. 5.5
Line Allocation
Maintenance
(33.5.17)

Line Allocation Maintenance		
User Menu Edit Queue Options Help		
Site: MILAN Milan, Italy		
Item Number: 0711 Rainbow Ice Cream		
UM: CS 2 KG -- 18 per Case		
Production Line	Description	Percent
001	Production Line 1	25.00%
002	Production Line 2	75.00%

Site. Enter the site code.

Item Number. Enter the end-item number.

UM. The screen displays the inventory unit of measure from the item master record.

Production Line. Enter the code for the item's production line at this site.

Description. The system displays the production line description from Production Line Maintenance (18.1.1).

Percent. Enter the production line allocation percentage. When you press Go, the system verifies that the total line percentage is 100%.

Use Line Allocation Inquiry (33.5.18) to view line allocations by site and item number.

Setting Target Inventory Levels

Operations planning calculates global target inventory levels to support an item's sales forecasts. In turn, it calculates production requirements based on target inventory levels.

If you do not specify otherwise, the system automatically sets each week's target inventory level to zero. In this case, you cannot build up inventory for future demands. You also cannot anticipate inventory shortages or surpluses.

There are three methods to establish global target inventory levels for end items:

- Calculate target inventory levels based on production demands exploded from the family plan. This is an easy method for items initially planned at the family level. No additional setup is required.

- Calculate target inventory levels based on manually recorded quantities. This method is precise. However, it is hard to maintain this information for many items because it changes constantly. Also, it offers no visibility to project shortages and surpluses.
- Calculate target inventory levels based on upcoming sales forecasts (weeks of coverage). For this method, you define global weeks-of-coverage factors for minimum, average, and maximum target inventory levels. This method requires more implementation effort. However, it does support inventory buildup for upcoming sales forecasts.

Note You can define coverage factors for either top-level family items or end items. However, to prevent the system from inflating inventory, do not set up coverage factors for both levels or for intermediate subfamily levels.

Table 5.1 illustrates how the system uses coverage factors on the operations plan. In the example, the system uses an average coverage factor of 2.0 to calculate the target inventory level.

No.	Sales Forecast	Target Inventory	Production Due	Projected QOH	Coverage
1	0	500	500	500	2.0
2	300	700	500	700	2.0
3	200	500	0	500	1.0
4	500	0	0	0	0.0

Table 5.1
Weeks of Coverage
on Operations Plan

When you change production due quantities on the plan, it uses the minimum (–) and maximum (+) factors to alert you to potential inventory shortages and surpluses relative to the average coverage level. This is illustrated in Table 5.2, which assumes a minimum coverage of 1.0 and a maximum of 3.0.

No.	Sales Forecast	Target Inventory	Production Due	Projected QOH	Coverage	
1	0	500	200	200	0.7	–
2	300	700	500	400	1.4	
3	200	500	0	200	0.4	–
4	500	0	0	–300	0.0	–

Table 5.2
Weeks of Coverage
on Operations
Plan—Production
Due Quantities
Changed

Loading Target Inventory Quantities

▶ See Chapter 6, “Data Collection,” on page 53.

There are two ways to load target inventory quantities manually:

- If you have already recorded target inventory quantities in a non-MFG/PRO eB database, use Item-Site Data Maintenance (33.13.3) and Item-Site Data Consolidation (33.13.6) to load them into MFG/PRO eB.
- Manually record quantities using Inventory Data Maintenance (33.13.17).

Setting Up Generic and Date-Specific Coverage Factors

▶ See “Setting Up Generic Coverage Factors” on page 38 and “Setting Up Date-Specific Coverage Factors” on page 39.

To set up generic and date-specific coverage factors for end-items, use the same programs described for setting up families. In the Item Number field, enter the end-item number. Coverage factors must be positive numbers. They can be either whole numbers or decimals.

Tracking Pallet Data

A pallet is a portable platform used to store and transport inventory. Some companies group items by pallet for operations planning. The Enterprise Operations Plan module does not use pallet information for calculations. However, you can record pallet information if your company needs it for reference or for use in an executive information system.

Setting Up Generic Pallet Information

Use Pallet Maintenance (33.5.20) to record generic pallet information. You can record dimensions and capacity for an unlimited number of pallet types.

Fig. 5.6
Pallet Maintenance
(33.5.20)

Pallet Maintenance	
User Menu Edit Queue Options Help	
Pallet Type: STANDARD	
Description:	Standard Pallet
Units per Layer:	18
UM:	CT
Number of Layers:	20
Height:	3.00
UM:	MT
Weight:	72.00
UM:	KG

Pallet Type. Enter a code (up to eight characters) for the pallet type.

Description. Enter the description of the pallet type.

Units per Layer. Enter the maximum number of inventory units that can be stored on this pallet type.

UM. The system displays the inventory unit of measure from the item master record.

Number of Layers. Enter the maximum number of layers this pallet type supports.

Height/UM. Enter the height and height unit of measure for the pallet type.

Weight/UM. Enter the weight and weight unit of measure for the pallet type.

Pallet Inquiry (33.5.21) displays information for one or all pallet types.

Setting Up Item Pallet Information

Use Item Pallet Maintenance (33.5.23) to customize pallet information for specific items.

Item Pallet Maintenance

User Menu Edit Queue Options Help

Pallet Type: STANDARD

Item Number: 0711 Rainbow Ice Cream

Description: Standard Pallet

Units per Layer: 36

UM: CT

Number of Layers: 10

Height: 3.00 UM: MT

Weight: 72.00 UM: KG

Fig. 5.7
Item Pallet
Maintenance
(33.5.23)

Pallet Type. Enter a code (up to eight characters) for the pallet type.

Item Number. Enter the end-item number.

Description. Enter the description of the pallet type.

Units per Layer. Enter the maximum number of inventory units that can be stored on this pallet type.

UM. The screen displays the inventory unit of measure from the item master record.

Number of Layers. Enter the maximum number of layers this pallet type supports.

Height/UM. Enter the height and height unit of measure for the pallet type.

Weight/UM. Enter the weight and weight unit of measure for the pallet type.

Use Item Pallet Inquiry (33.5.24) to view information for one or all item pallet types.

CHAPTER 6

Data Collection

This chapter describes data collection activities used for both family and end-item planning.

Introduction **54**

Loading Data from MFG/PRO eB Databases **55**

Loading Data from Non-MFG/PRO eB Databases **59**

Maintaining Loaded Data **61**

Routing Code: 10-15000 OPERATION: 20 NAME: (75) COOLING

Standard Operation	10.30	INSPECTION, ALL SITES
Work Center		
Machine		
Description	INSPEC PER PROX-005	
Machines per Op	1	Allocation
Overlap Units	1	
Queue Time	1.0	
Wait Time	0.0	
Setup Time	0.0	

Route by Production Route

Introduction

Operations planning consolidates and transforms transaction information from all company sites into a central database. Family plans and operations plans use sales forecast and on-hand inventory quantities. Performance measurement reporting also uses actual production and purchase order receipt quantities.

Before you can calculate plans or print reports, you must load this information into the Enterprise Operations Plan module of the central planning site. The load generates records that summarize the original item numbers, quantities, and transaction effective dates at the time of the load.


Table 6.1
Operations Data to
Be Loaded

To Generate	Collect
Family plans	Sales forecasts (only for family plans based on end-item sales forecasts)
	Beginning inventory balances
Operations plans	Sales forecasts
	Beginning inventory balances (only for multilevel operations plans)
	MRP gross requirements
Performance reports	Actual sales shipments
	End-item inventory balances
	Completed work orders
	Completed repetitive schedules
	Purchase order receipts

In many respects, Operations Plan is a separate environment from other modules. Changes you record in Operations Plan do not update original sales forecasts, inventory balances, or other data. Also, changes you record in other modules do not update previously loaded quantities (unless you reload). This approach gives you a secure central planning environment.

Figure 6.1 summarizes the data collection work flow.

Fig. 6.1
Data Collection
Work Flow



Loading Data from MFG/PRO eB Databases

Loading data from MFG/PRO eB databases is a one-step process that transfers the data directly from the source modules into the Enterprise Operations Plan module.

To load data from MFG/PRO eB databases, use Transaction Data Load (33.13.1). This program collects end-item sales, inventory, and production data for sites in all connected MFG/PRO eB databases. Table 6.2 summarizes load options.

Table 6.2
Transaction Data
Load Options

To Generate	Set
Operations plans based on family plans	Update Inventory QOH: Yes
Family plans and operations plans based on end-item sales forecasts	Update Sales Forecasts: Yes
	Update Inventory QOH: Yes
Performance measurement reports	Update Actual Sales: Yes
	Update Actual Production: Yes
	Update Inventory QOH: Yes

To include purchase order receipts in loaded inventory balances and actual production, set Include PO Receipts to Yes. To include non-nettable inventory in loaded inventory balances, set Include Non-Nettable Inventory to Yes.

You can rerun the load as many times as necessary. Each load overwrites the effects of previous loads.

Fig. 6.2
Transaction Data
Load (33.13.1)

Item Number:	0711	To:	0711
Site:	LONDON	To:	LONDON
Effective:	06/10/96	To:	06/30/96
Product Line:			
Item Group:			
Item Type:			
Update Sales Forecasts:	yes		
Use Gross Requirements:	no		
Update Actual Sales:	no		
Update Actual Production:	no		
Include PO Receipts:	no		
Update Inventory QOH:	yes		
Include Non-Nettable Inventory:	no		
		Output:	printer
		Batch ID:	

Item Number/To. Enter the end-item range. The load does not collect data for family items.

Site/To. Enter the site range.

Effective/To. Enter the effective date range for the load. When you specify a non-Monday start date or a non-Sunday end date, the system changes it. To load inventory quantities for a planning week, you must set the effective date to the Monday of the previous week. The ending inventory of the prior week becomes the beginning projected available inventory for the current planning week.

Product Line. Enter the end-item product line.

Item Group. Enter the item group. This code is useful for choosing items for processing. For example, you can use it to segregate items included in operations planning from those that are not.

Item Type. Enter the item type. This code is useful for choosing items for processing. For example, you can use it to segregate items included in operations planning from those that are not.

Update Sales Forecasts. Enter Yes to load end-item sales forecasts for the family plan or operations plan. Enter No if you develop the operations plan using sales forecasts generated by Family Plan Explosion (33.7.14).

Use Gross Requirements. Enter Yes to load gross requirements for multilevel operations planning. Source Matrix Explosion (33.13.8) will then use gross requirements from the most recent materials plan to calculate target inventory levels for component items.

Update Actual Sales. Enter Yes to load sales shipments for performance measurement reporting.

Update Actual Production. Enter Yes to load completed work orders and completed repetitive schedules for performance measurement reporting.

Include PO Receipts. Enter Yes to include purchase order receipts and shipper confirmations in loaded inventory balances and actual production quantities.

Update Inventory QOH. Enter Yes to load beginning on-hand inventory balances as of 00:01 of the Monday starting effective date.

Include Non-Nettable Inventory. Enter No to exclude non-nettable inventory from loaded inventory balances. You can access this field only when Update Inventory QOH is Yes. Non-nettable quantities are normally excluded because they are defective, in transit, or reserved. Enter Yes to include them.

Output. Enter the output for the report—terminal, printer, or ASCII file name.


Batch ID. If you enter a batch ID, the system does not run this process immediately. It puts the request in a queue for batch processing.

Planning for Multilevel Operations

Transaction Data Load (33.13.1) has another useful application in companies that calculate operations plans for components as well as end items. You can use the Use Gross Requirements option to collect MRP gross requirements for the components, so that the operations plan includes the components as well as the end items.

Example Premium Ice Cream Company makes ice cream bars sold in packages of 6 and 12. The ice cream bars are an end item when sold individually, but a component when sold in packages. An operations plan is generated at both the bar and package levels. In Transaction Data Load (33.13.1), Gross Requirements is Yes. The system adds forecast data to the gross requirements data to determine the operations plan requirements. Figure 6.3 illustrates this multilevel planning situation.

Fig. 6.3
Multilevel
Operations
Planning



For multilevel operations planning:

- 1 Enter sales forecasts to record all independent demands for the end item and the component.
- 2 Run MRP to calculate the gross requirements—the dependent demands for the end-item forecasts.
- 3 Use Transaction Data Load (33.13.1) to load the planning data. To load the sales forecasts, set Update Sales Forecasts to Yes. To load the MRP gross requirements, set Use Gross Requirements to Yes.

Loading Data from Non-MFG/PRO eB Databases

Loading data from non-MFG/PRO eB databases is a distributed process. You can review and correct data as you load it into MFG/PRO eB, and then again after you load it into the Enterprise Operations Plan module.

Loading Item-Site Data

You can record data in Item-Site Data Maintenance (33.13.3) manually. However, to load many records, it is more efficient to generate an ASCII file from the source database, then use the CIM programs in the Manager Functions module to load the file into Item-Site Data Maintenance (33.13.3).

▶ See *User Guide Volume 9: Manager Functions* for information on CIM.

Fig. 6.4
Item-Site Data Maintenance (33.13.3)

Item Number. Enter the end-item number.

Site. Enter the site code.

Data Type. Enter F (sales forecasts), S (actual sales), W (actual production), P (production due), or I (on-hand inventory balances).

Effective. Enter the effective date for including the loaded data in operations planning calculations. When loading inventory quantities, you must set the effective date to the previous Monday.

Quantity. Enter the item quantity to load.

Reference. Optionally, enter a comment about the item quantity. This comment prints on the Item-Site Data Report (33.13.5).

Use two programs to view loaded item-site records.

- Item-Site Data Inquiry (33.13.4) shows records by item number, site, and data type.

- Item-Site Data Report (33.13.5) is similar, but you can select ranges of items, sites, and effective dates.

Consolidating Loaded Data

After you load data, you must consolidate the loaded item quantities into weekly buckets. Operations planning requires these to generate family plans, operations plans, and performance reports.

After you successfully consolidate, reduce the database size by rerunning the consolidation program to delete the original load records.

Use Item-Site Data Consolidation (33.13.6) to consolidate the loaded data.

Fig. 6.5
Item-Site Data
Consolidation
(33.13.6)

Run a second time with this field set to Yes to save space in the database.

Site/To. Enter the site range.

Item Number/To. Enter the item number range.

Delete Item-Site Load Records. Enter Yes to delete previously consolidated item-site operations planning records. Do not do this until you have completed operations planning processing for the planning period.

Include Previously Loaded Records. Enter Yes to include previously consolidated records in this process.

Output. Enter the output for the report—terminal, printer, or ASCII file name.

Batch ID. If you enter a batch ID, the system does not run this process immediately. It puts the request in a queue for batch processing.

Maintaining Loaded Data

After you load planning data, review it before calculating plans or printing reports. Correct errors or update operations planning records for significant transaction changes that occurred after you loaded data.

Note Changes made in the Operations Plan do *not* update transaction records in other modules or in other databases.

Changing Sales Data

To change previously loaded forecast or shipment quantities, use Sales Data Maintenance (33.13.13). You can also use this program (manually or with CIM) to record sales quantities.

By default, the screen displays item information in calendar weeks, but you can switch to general ledger periods.

Warning If you normally plan in weeks, do not change quantities in period view. If you do, the system permanently reassigns all weekly quantities to the first week of each period.

See *User Guide Volume 9: Manager Functions* for information on CIM.

Sales Data Maintenance						
User Menu Edit Queue Options Help						
Site: LONDON London, England Start: 06/10/96						
Item Number: 0711 Rainbow Ice Cream 2 KG -- 18 per Cas						
Bucket: W Nbr: 24 UM: CS						
Week	Nbr	Sales Fcst	Actual Sales	Variance	Variance %	
06/10/96	24	1500.00	0.0	0.0		
06/17/96	25	2000.00	0.0	0.0		
06/24/96	26	2200.00	0.0	0.0		
07/01/96	27	0.00	0.0	0.0		
07/08/96	28	0.00	0.0	0.0		
07/15/96	29	0.00	0.0	0.0		
07/22/96	30	0.00	0.0	0.0		
07/29/96	31	0.00	0.0	0.0		
08/05/96	32	0.00	0.0	0.0		
08/12/96	33	0.00	0.0	0.0		
08/19/96	34	0.00	0.0	0.0		
08/26/96	35	0.00	0.0	0.0		

Fig. 6.6
Sales Data
Maintenance
(33.13.13)

- Site. Enter the site code.
- Start. Enter the start date for the first calendar week or financial period. The default start date is the system date. If the date you enter

is not the Monday of the week or the first day of the period, the system changes it.

Item Number. Enter the item number.

Bucket. Enter W to group item quantities into calendar weeks that start on Mondays. Enter P to group quantities into financial periods with a start date that is the first day of the period.

Nbr. Enter the number of the first calendar week or financial period to display. If you enter a bucket number instead of a start date, the system fills in the start date for you. The system also changes the start date to the first day of this week or period if this day is not already the start date.

UM. Enter the unit of measure for viewing and changing item quantities. The default unit of measure is from the item master record.

Sales Fcst. Enter the sales forecast quantity to update. Sales orders that consume forecasts do not automatically reduce these sales forecast totals.

Actual Sales. Enter the sales shipment quantity to update. You can update this only in week view. In period view, the system cannot associate shipments back to the correct week.

Variance. When you change item quantities, the screen recalculates quantity variances between planned and actual performance.

Variance %. When you change item quantities, the screen recalculates percentage variances between planned and actual performance.

Reviewing Sales Data

Use two programs to view sales data:

- Sales Data Inquiry (33.13.14) shows sales forecast and actual sales shipment quantities by item-site.
- Sales Data Report (33.13.15) is similar, but you can select ranges of items, sites, and planning periods, and the unit of measure to display quantities.

Changing Inventory Data

To change previously loaded target inventory levels or on-hand inventory balances, use Inventory Data Maintenance (33.13.17). You can also use this program (manually or with CIM) to record inventory quantities.

By default, the screen displays item information in calendar weeks, but you can switch to GL periods.

Warning If you normally plan in weeks, do not change quantities in period view. If you do, the system permanently reassigns all weekly quantities to the first week of each period.

See *User Guide Volume 9: Manager Functions* for information on CIM.

Week	Nbr	Target Inv	Actual QOH	Variance	Variance %
06/10/96	24	0.00	150.0	0.0	
06/17/96	25	0.00	0.0	0.0	
06/24/96	26	0.00	0.0	0.0	
07/01/96	27	0.00	0.0	0.0	
07/08/96	28	0.00	0.0	0.0	
07/15/96	29	0.00	0.0	0.0	
07/22/96	30	0.00	0.0	0.0	
07/29/96	31	0.00	0.0	0.0	
08/05/96	32	0.00	0.0	0.0	
08/12/96	33	0.00	0.0	0.0	
08/19/96	34	0.00	0.0	0.0	
08/26/96	35	0.00	0.0	0.0	

Fig. 6.7
Inventory Data Maintenance (33.13.17)

This program is very similar to Sales Data Maintenance (33.13.13). Only two fields are different:

Target Inv. Enter the target inventory quantity to update.

Actual QOH. Enter the actual inventory balance to update. You can update this only in week view. In period view, the system cannot associate balances back to the correct week.

Important If you record or change target inventory levels for the operations plan, you must set Calculate Target Inventory Level to No when you run Source Matrix Explosion (33.13.8). Otherwise, the explosion will overwrite your changes.

See “Changing Sales Data” on page 61.

Reviewing Inventory Data

Use two programs to view inventory data:

- Inventory Data Inquiry (33.13.18) shows target inventory levels and actual on-hand inventory quantities by item-site.
- Inventory Data Report (33.13.19) is similar, but you can select ranges of items, sites, and planning periods, and the unit of measure to display quantities.

Changing Production Data

See *User Guide Volume 9: Manager Functions* for information on CIM.

To change previously loaded production due or actual production quantities, use Production Data Maintenance (33.13.21). You can also use this program (manually or with CIM) to record production quantities.

By default, the screen displays item information in calendar weeks, but you can switch to GL periods.

Warning If you normally plan in weeks, do not change quantities in period view. If you do, the system permanently reassigns all weekly quantities to the first week of each period.

Fig. 6.8
Production Data Maintenance (33.13.21)

Production Data Maintenance						
User Menu Edit Queue Options Help						
Site: MILAN		Milan, Italy		Start: 06/10/96		
Item Number: 0711		Rainbow Ice Cream		2 KG -- 18 per Cas		
Bucket: W		Nbr: 24		UM: CS		
Week	Nbr	Production Due	Actual Production	Variance	Variance %	
06/10/96	24	2000.00	0.0	-2,000.0	-100.00	
06/17/96	25	1500.00	0.0	-1,500.0	-100.00	
06/24/96	26	2200.00	0.0	-2,200.0	-100.00	
07/01/96	27	0.00	0.0	0.0		
07/08/96	28	0.00	0.0	0.0		
07/15/96	29	0.00	0.0	0.0		
07/22/96	30	0.00	0.0	0.0		
07/29/96	31	0.00	0.0	0.0		
08/05/96	32	0.00	0.0	0.0		
08/12/96	33	0.00	0.0	0.0		
08/19/96	34	0.00	0.0	0.0		
08/26/96	35	0.00	0.0	0.0		

See “Changing Sales Data” on page 61.

This function is very similar to Sales Data Maintenance (33.13.13). Only two fields are different:

Production Due. Enter the production due quantity to update.

Actual Production. Enter the actual production quantity to update. You can update this only in week view. In period view, the system cannot associate quantities back to the correct week.

Important If you record or change production due quantities for the operations plan, you must set Calculate Production Due to No when you run Source Matrix Explosion (33.13.8). Otherwise, the explosion will overwrite your changes.

Reviewing Production Data

Use two programs to view production data:

- Production Data Inquiry (33.13.22) shows production due and actual production quantities by item-site.
- Production Data Report (33.13.23) is similar, but you can select ranges of items, sites, and planning periods, and the unit of measure to display quantities.

Family-Level Planning

This chapter describes the operations planning cycle for product families.

Introduction **68**

Calculating Family Plans **69**

Maintaining Family Plans **70**

Exploding Family Plans **76**

Rolling Up End-Item Changes **78**

param91.p 14.13.2 Routing Maintenance (Main Screen)

Routing Code:	10-15000	NONAD(75) CDR IN
Operation:	20	
Standard Operation		
Work Center	1030	INSPECTION, ALL SITE
Machines		
Description	INSPEC PER PROX-005	
Machines per Op	1	Milestone
Overlap Units	1	
Queue Time	1.0	
Wait Time	0.0	
Setup Time	0.0	

Route by Production Route


Introduction

Companies typically do family-level operations planning in a long- to medium-term time frame, usually six months to three years. They use it to:

- Project long-term labor, equipment, and financial commitments.
- Develop long-term material procurement plans for negotiations with strategic suppliers.

MFG/PRO eB maintains an operations plan for every family item. This plan shows sales forecasts, target inventory levels, and production demands for the planning horizon. You can view the plan from the global and site levels.

Fig. 7.1
Family Processing
Work Flow



▶ See *User Guide Volume 3: Manufacturing*.

▶ See Chapter 6, “Data Collection,” on page 53.

For long-term planning, use Forecast Maintenance (22.1) to record sales forecasts by family and marketing site.

For medium-term planning, use the programs on the Item-Site Consolidation menu (33.13) to load existing end-item sales forecasts and inventory balances into the Enterprise Operations Plan module.

Calculating Family Plans

Run Global Consolidation (33.7.1) to calculate the family plan. The consolidation totals marketing site sales forecasts to the global level and calculates the required target inventory and production due quantities. This plan can be based on either family or end-item sales forecasts.

- By default, the family plan is based on family-item forecasts recorded in Forecast Maintenance (22.1). The consolidation collects these from all sites in connected MFG/PRO eB databases. If you have forecasts in non-MFG/PRO eB databases, load them into Forecast Maintenance in the operations planning database using the CIM load process. You typically use this method for longer-term planning.
- To roll up and consolidate end-item forecasts, first load them, plus beginning inventory balances, into the Enterprise Operations Plan module using either Transaction Data Load (33.13.1) or Item-Site Data Maintenance (33.13.3). You typically use this method for shorter-range planning.

See Chapter 6, “Data Collection,” on page 53.

You can recalculate the family plan as many times as necessary. Each calculation overwrites the effects of the previous one.

Before you load or consolidate data for the family plan, you can review planning data for family items or end items.

- To review sales forecasts, use Forecast Inquiry (22.3) or Forecast Report (22.4).
- To review inventory balances, use Stock Availability Inquiry (3.17).




Fig. 7.2
Global Consolidation (33.7.1)

Family Item. Enter the family item number.

Site/To. Enter the site range.

Year/To. Enter a maximum range of three calendar years, starting with the current year.

Roll Up End Items. Enter Yes to calculate global family sales forecast from end-item forecasts and to roll up end-item inventory quantities to the family level. The rollup starts from the end-item level at the bottom of the hierarchy and works upward to the top-level family item, performing a unit-of-measure conversion at each subfamily level. The rollup also calculates the actual percentage of sales forecast that each end item or subfamily in the family-site hierarchy contributes to the family forecast. Enter No to consolidate site-level family forecasts.

Include Actual Inventory in Calculation. If Roll Up End Items is Yes, indicate whether the system should include on-hand inventory quantities for those items in the forecast calculations.

Output. Enter the output for the report—terminal, printer, or ASCII file name.

Batch ID. If you enter a batch ID, the system does not run this process immediately. It puts the request in a queue for batch processing.

Maintaining Family Plans

After you consolidate, review the family plan and verify the production due quantities against available resource capacity. Adjust production due as necessary.

Operations Plan Resource Inquiry (33.15.21) displays projected resource load for the family plan production due quantity.

Fig. 7.3
Operations Plan
Resource Inquiry
(33.15.21)

Operations Plan Resource Inquiry							
User Menu Edit Queue Options Help							
Item Number	Site	Resource	Start	End	Per	Output	
0510		BLENDER	06/10/96		1	terminal	
Past 06/10/96 06/17/96 06/24/96 07/01/96 07/08/96 07/15/96							
06/09/96 06/16/96 06/23/96 06/30/96 07/07/96 07/14/96 07/21/96							
Workdays	0	25	25	25	25	25	25
Capacity	0	18,000	18,000	18,000	18,000	18,000	18,000
Load	0	0	1,500	2,000	2,500	3,000	0
Over/Under	0	18,000	16,500	16,000	15,500	15,000	18,000
Cumulative	0	18,000	34,500	50,500	66,000	81,000	99,000

Item Number. Enter the item number. To review resource load for all items that use this resource, leave blank.

Site. Enter the site code.

Resource. Enter the code of the critical resource to review.

Start. Enter the start date for reviewing information. The default start date is Monday of the current week.

End. Enter the end date for including information. The default end date is blank.

Per. Enter the multiple to use for resource load calculations. By default, the system calculates resource load based on actual available workdays and resource capacity ($\text{Per} = 1$). But you can reset this multiple to see how load would balance against additional capacity. The formula is:

(Production Due x Resource Quantity Per) ÷ Per x (Workdays x Resource Capacity)

Output. Enter the output for the report—terminal, printer, or ASCII file name.

Press Go to view the lower half of the screen.

Workdays. The number of days in the shop calendar week, as defined in Calendar Maintenance (36.2.5).

Capacity. The weekly capacity for the resource, calculated as:

Workdays in the Weekly Shop Calendar x Daily Resource Capacity

The shop calendar is defined in Calendar Maintenance (36.2.5).

Resource capacity is defined in Resource Maintenance (21.1).

Load. The weekly production load for the specified resource, calculated as:

Production Due Quantity x Resource Quantity Per

You can adjust production due in Operations Plan Maintenance (33.15.1). Resource quantity per is defined in Item Resource Bill Maintenance (21.17).

Over/Under. Each week's capacity shortages and availability, calculated as:

Capacity – Load


Cumulative. The total capacity shortage or availability for the resource. This number varies, based on the start date you specify.

Tip

Negative figures denote shortages and positive figures denote available capacity.

Press Go again to display a graphical view of the load data.

Fig. 7.4
Operations Plan
Resource Inquiry,
Graph View



Load Percentage of Capacity. The graph shows the percentage of capacity already consumed by projected load, calculated as:

$$\text{Production Load} \div \text{Weekly Resource Capacity}$$

Changing Family Plans

Use Global Production Maintenance (33.7.3) to view the plan and change production due quantities. You can also delete a family plan, either for an entire year, or for only specific periods within the year—for example, if an item becomes obsolete.

You can manipulate the plan at either the global or site levels. Except for sales forecasts, calculations of global and site quantities are the same.

Display item information either by calendar week or by GL period. If you normally plan in weeks, do not change production quantities in period view. If you do, the system permanently reassigns all weekly quantities to the first week of the period.

To delete a plan for an entire year, select the plan and press Delete. To delete a plan for part of the year, reset the production due quantities to zero for the affected period.

This program updates only the planning database. Other databases do not have to be connected.

Date	Nbr	Sales Fcst	Target Inv	Prod Due	Proj QOH	Cov
06/10/96	24	0.00	0.0	0.00	0.0	0.0
06/17/96	25	1500.00	0.0	1500.00	0.0	0.0
06/24/96	26	2000.00	0.0	2000.00	0.0	0.0
07/01/96	27	2500.00	0.0	2500.00	0.0	0.0
07/08/96	28	3000.00	0.0	3000.00	0.0	0.0
07/15/96	29	0.00	0.0	0.00	0.0	0.0
07/22/96	30	0.00	0.0	0.00	0.0	0.0
07/29/96	31	0.00	0.0	0.00	0.0	0.0
08/05/96	32	0.00	0.0	0.00	0.0	0.0
08/12/96	33	0.00	0.0	0.00	0.0	0.0
08/19/96	34	0.00	0.0	0.00	0.0	0.0
08/26/96	35	0.00	0.0	0.00	0.0	0.0

Fig. 7.5
Global Production
Maintenance
(33.7.3)

Family Item. Enter the number of a top-level family item. You cannot change subfamily quantities in this screen.

All Sites. Enter Yes to display the global production due quantity for this family item. Enter No to display the quantity for one site.

Site. Enter the marketing site code. You can access this field only if All Sites is Yes.

Start. Enter the start date for the first calendar week or financial period. The default start date is the system date. If the date you enter is not the Monday of the week or the first day of the period, the system changes it.

Bucket. Enter W to group item quantities into calendar weeks that start on Mondays. Enter P to group quantities into financial periods with a start date that is the first day of the period.

Nbr. Enter the number of the first calendar week or financial period to display. If you enter a bucket number instead of a start date, the system fills in the start date for you. The system also changes the start date to the first day of this week or period if this day is not already the start date.

UM. Enter the unit of measure for viewing and changing item quantities. The default unit of measure is the one from the item master record.

Opening QOH. The screen displays the total opening on-hand inventory balance for all end items in the family. However, the system does not use this to calculate production due quantities.

Sales Fcst. Global sales forecast is the family forecast for all marketing sites in the family hierarchy. Site sales forecast is the family forecast for one marketing site. If you consolidated the plan using the Roll Up End Items option, family forecasts were calculated from forecasts for the end items in the family.

Target Inv. Target inventory level is the desired level of coverage specified by the family's average weeks-of-coverage factor. This quantity will be either this week's forecast, if the coverage factor is zero, or the total forecast for the number of upcoming weeks specified by the average coverage factor.

Prod Due. The screen displays the family item's projected production demand. The formula is:

$$(Sales Forecast + Target Inventory) - Previous Week's Projected QOH$$

For family items, previous projected QOH is zero for the first week, and production due is gross (not netted against on-hand inventory). When you change global production due (All Sites is Yes), the system recalculates global projected quantity on hand and weeks of coverage. It also distributes the effects of the change proportionately to all marketing sites.

Proj QOH. Initially, projected quantity on hand equals the target inventory level. When you change production due, the system recalculates it as:

$$(Previous Week's Projected QOH + Production Due) - Sales Forecast$$

For the first week, the projected QOH is the opening QOH.

Cov. Initially, projected weeks of coverage is the item's average weeks-of-coverage factor. When you change production due, the system recalculates this, using the item's minimum and maximum coverage factors to project inventory shortages (–) and surpluses (+) relative to the average weeks of coverage. An asterisk (*) indicates

that projected coverage satisfies the maximum coverage requirement specified in Operations Plan Control File (33.1.24).

Use two programs to review family plans:

- Global Production Inquiry (33.7.4) shows the global or site plan for the specified family item. To review the global plan, leave site blank. You can select the starting week or period and unit of measure to view quantities.
- Global Production Report (33.7.5) is similar, but you can select ranges of family items, sites, and effective years.

Reviewing Projected Profit

As you balance the plan, use Profit Projection Report (33.7.16) to assess the potential profitability of family sales, inventory, and production. The program calculates potential gross margin associated with a family item’s sales forecasts, target inventory levels, or planned production. It calculates gross margin as price minus cost.

You can view this report in different currencies and in weeks or periods. Select summary or detail mode. Summary mode shows total item-site quantity, cost, and price for the selected weeks/periods. Detail mode shows this information for each week or period.




Fig. 7.6
Profit Projection
Report (33.7.16)


Exploding Family Plans

After you are satisfied with the family plan, explode the dependent end-item demands out to the marketing sites. This automatically transfers control of the family production demands to the end-item level for subsequent planning and execution.

Figure 7.7 summarizes the explosion calculation, using a UM conversion of 1 metric ton = 27.778 cases. Starting from the top-level family, the explosion calculates the dependent demands for each subfamily and marketing site, converting units of measure between levels as necessary. The system stores the resulting end-item demands as sales forecast demands in the Enterprise Operations Plan module.

If you generated the family plan from family-level forecasts, use the Balance Forecasts for DRP option to preserve the link between the end-item demands and their respective marketing sites.

Fig. 7.7
Explosion
Calculation



Reviewing Family Forecast Percentages

Before you explode the family plan, use Rollup Percentage Report (33.7.7) to compare planned and calculated forecast percentages. The report displays the family hierarchy's forecast percent along with the actual forecast percentages for the upcoming six weeks. The report sorts by hierarchy and subfamily level.




Fig. 7.8
Rollup Percentage
Report (33.7.7)

Exploding Family Plans

Run Family Plan Explosion (33.7.14) only when you are ready to transfer control of the family production quantities down to the end-item level.

Important Do not record forecast quantities in Sales Data Maintenance (33.13.13) for the end items in the family before running Family Plan Explosion. If you do, the explosion will overwrite them. However, you can adjust forecast quantities after running the explosion.




Fig. 7.9
Family Plan
Explosion (33.7.14)

Family Item. Enter the family item number.

Year/To. Enter a maximum range of three calendar years, starting with the current year.

Effective. Enter the start date for including family plan quantities in the explosion. The default date is the Monday of the current week. For planning periods after this date, the explosion generates dependent demands from the family gross production quantities. It also overwrites existing end-item forecast quantities for these periods. The explosion ignores forecast quantities for planning periods prior to the date.

◆ See “Roll Up End Items” on page 70.

Use Calc Fcst Pct. Enter Yes to explode the plan based on actual forecast percentages updated by Global Consolidation (33.7.1). Do this if you used the Roll Up End Items option during the consolidation. Otherwise, enter No to use the subfamily percentages from Family Hierarchy Maintenance (33.3.1). To compare the two percentages, review the Rollup Percentage Report (33.7.7).

Balance Forecasts for DRP. If you generated the family plan from family forecasts, you must set this option to Yes. The explosion then generates sales forecast records for the end-item production demands. If you do not set this option, you will not be able to trace production demands back to their respective marketing sites because DRP will not generate intersite requests for family production demands.

Explode Family Item Target Inventory. If Yes, target inventory calculated at the family level is exploded down the family hierarchy tree to the end-item level. If No, only family level inventory is calculated.

If you set this field to Yes here, make sure you set Calculate Target Inventory Level to No in Source Matrix Explosion (33.13.8). Otherwise, the end-item target inventory calculated by this program will be overwritten.

Output. Enter the output for the report—terminal, printer, or ASCII file name.

Batch ID. If you enter a batch ID, the system does not run this process immediately. It puts the request in a queue for batch processing.

Rolling Up End-Item Changes

Throughout the planning process, it is important to update the family plan whenever you make changes at the end-item level. For example, you must do this whenever you change the operations plan, or you may produce too much or too little in a future week. When you update the family plan, the system converts the end-item quantity back into the equivalent family item quantity.

The system does not automatically update the family plan. You must roll up changes:

- After you finish updating operations plans for each week or period.

- Before you print performance measurement reports.

Figure 7.10 summarizes the rollup calculation, using a UM conversion of 1 case = 0.036 metric tons. The rollup updates the family projected weeks of coverage and projected quantity on hand in the family plan. For performance reporting, it also calculates the planned/actual variances and updates the actual percentage of sales in the family hierarchy.




Fig. 7.10
Rollup Calculation

To ensure that the operations plan and family plan remain balanced, sites must define and enforce rigid procedures for executing the rollup.

Running Family Plan Rollup

Use Family Plan Rollup (33.7.13) to roll up changes. The rollup converts end-item quantities to family item quantities based on the percentages specified in the family hierarchy. It also converts quantities to the family unit of measure, at all subfamily levels of the hierarchy.

Be sure to select all sites and years affected by the end-item changes. The rollup includes changes for all end items in the family hierarchy.

Fig. 7.11
Family Plan Rollup
(33.7.13)

Family Plan Rollup

User Menu Edit Queue Options Help

Family Item: 0510

Site: GENEVA To: PARIS

Year: 1996 To: 1996

Output:
Batch ID:

Family Item. Enter the family item number.

Site/To. Enter the site range.

Year/To. Enter a maximum range of three calendar years, starting with the current year.

Output. Enter the output for the report—terminal, printer, or ASCII file name.

Batch ID. If you enter a batch ID, the system does not run this process immediately. It puts the request in a queue for batch processing.

CHAPTER 8


End-Item Planning

This chapter describes the operations planning cycle for end items.

Introduction **82**

Calculating Operations Plans **83**

Maintaining Operations Plans **86**



Routing Maintenance (Main Screen)

Routing Code:	10-15000	NONAD (75) COOLING
Operation:	20	
Standard Operation		
Work Center	1030	INSPECTION, ALL SITES
Machine		
Description	INSPEC PER PROC-005	
Machines per Op	1	Milestone
Overlap Units	1	
Queue Time	1.0	
Wait Time	0.0	
Setup Time	0.0	

Route by Production Build Order

Introduction

Companies typically do end-item operations planning in a short- to medium-term time frame, usually zero to six months. They use it to:


- Optimize target inventory and production levels throughout the enterprise.
- Develop production schedules for supply sites and production lines.
- Identify variances between planned and actual performance.

MFG/PRO eB maintains an operations plan for every end item. This plan shows global sales forecasts and target inventory levels and site-level production demands for the planning horizon. The end-item operations plan is the equivalent of a master production schedule.

Important If you use the Enterprise Operations Plan module for master scheduling, do *not* use the Forecast/Master Plan module for the same item-site.

Figure 8.1 shows how calculating and maintaining the operations plan fit into the overall family plan process.

Fig. 8.1
End-Item
Processing Work
Flow



Calculating Operations Plans

To calculate an item's operations plan, you run Source Matrix Explosion (33.13.18). This program calculates global sales forecasts, target inventory levels, and production due. It distributes production due to supply sites and production lines based on the percentages you have defined in the item source matrix and site line allocations.

Example A company defines a source matrix for an item specifying production of 50% in Dublin and 50% in Milan. Total production due of the item is 1500 cases. The Milan site defines site line allocations of 25% to Line 1 and 75% to Line 2. Figure 8.2 summarizes the explosion calculation.




Fig. 8.2
Explosion
Calculation

Several factors influence how the explosion calculates production quantities and due dates:

- The explosion assumes infinite capacity.
- By default, the explosion calculates an item's target inventory levels and production due based on upcoming sales forecasts and beginning on-hand inventory balances. However, you can set the explosion to simply consolidate manually recorded target inventory levels or even production due dates loaded from individual sites.
- You can set the explosion to adjust production due quantities based on item-site MRP order modifiers. You can also prevent the explosion from changing production due inside the item-site time fence.

- When scheduling production, the explosion automatically considers item-site lead times—safety, inspection, purchasing, and manufacturing.
- The explosion does not schedule production for non-production weeks if Move Holiday Production Backward is Yes in the Operations Plan Control File (33.1.24), but reschedules production backward to the Monday of the first available working week. The control file setting does not affect production scheduling for working weeks with holidays.

Running Source Matrix Explosion

Tip

The explosion takes a long time and is best run in batch.

Run Source Matrix Explosion (33.13.8) to calculate the operations plan. If necessary, you can rerun the explosion. Subsequent explosions completely overwrite the effects of previous ones.

Fig. 8.3
Source Matrix
Explosion (33.13.8)

Item Number/To. Enter the item number range.

Effective/To. Enter the effective date range. When you specify a non-Monday start date or a non-Sunday end date, the system changes it.

Buyer/Planner. If you specify a value, the system processes only items assigned to this person.

Product Line. If you specify a value, the system processes only items belonging to this product line.

Item Group. If you specify a value, the system processes only items belonging to this item group.

Item Type. If you specify a value, the system processes only items belonging to this item type.

Calculate Target Inventory Level. Enter Yes to calculate target inventory levels based on item average weeks-of-coverage factors. Enter No to prevent the explosion from overwriting target inventory quantities recorded or adjusted in Inventory Data Maintenance (33.13.17).

Calculate Production Due. Enter Yes to calculate each item's production due quantity. Enter No to prevent the explosion from overwriting quantities recorded or adjusted in Production Data Maintenance (33.13.21).

Use MRP Order Policies. Enter Yes to adjust calculated production due quantities based on the supply site's item order policies and order modifiers. Enter No to calculate production due independent of these factors.

Use Planning Time Fence. Enter Yes to prevent the explosion from recalculating production quantities due within the item-site time fence period. This setting protects the master schedule against last-minute orders with a cumulative lead time that exceeds the available production time. Enter No to permit recalculations.

Include Actual Inventory in Calculation. When the global family sales forecast is calculated by Global Consolidation (33.7.1) by rolling up end items, you can choose to include or exclude the opening inventory balance in the calculation. This flag has the same effect when the plan is exploded out. The field is typically set the same way in both programs.

Output. Enter the output for the report—terminal, printer, or ASCII file name.

Batch ID. If you enter a batch ID, the system does not run this process immediately. It puts the request in a queue for batch processing.

Maintaining Operations Plans

After you run the explosion, review the operations plan and verify the production due quantities against available resource capacity. Adjust production due as necessary.

Reviewing Projected Resource Load

▶ See page 70 for details.

Use Operations Plan Resource Inquiry (33.15.21) to display projected resource load for the family plan production due quantity.

Changing Site Operations Plans

If you are a central master scheduler, use Operations Plan Maintenance (33.15.1) to view global sales forecasts and target inventory levels and to adjust production due quantities for individual supply sites. As you change quantities, the system recalculates projected quantity on hand and projected weeks of coverage.

You can also delete an operations plan, either for an entire year, or for only specific periods within the year—for example, if an item becomes obsolete.

You can display item information either by calendar week or by general ledger period. If you normally plan in weeks, do not change production quantities in period view. If you do, the system permanently reassigns all weekly quantities to the first week of the period.

To delete a plan for an entire year, choose the plan and press Delete. To delete a plan for part of the year, reset the production due quantities to zero for the affected period.

Operations Plan Maintenance

User Menu Edit Queue Options Help

Site: MILAN Milan, Italy Start: 06/10/96

Item Number: 0711 Rainbow Ice Cream 2 KG -- 18 per Cas

Bucket: W Nbr: 24 UM: CS Opening QOH: 0.0

Date	Nbr	Sales Fcst	Target Inv	Prod Due	Proj QOH	Cov
06/10/96	24	0.00	1,500.0	750.00	1,500.0	2.0
06/17/96	25	750.00	1,250.0	250.00	1,250.0	2.0
06/24/96	26	750.00	1,000.0	250.00	1,000.0	2.0
07/01/96	27	500.00	500.0	0.00	500.0	1.0
07/08/96	28	500.00	0.0	0.00	0.0	0.0
07/15/96	29	0.00	0.0	0.00	0.0	0.0
07/22/96	30	0.00	0.0	0.00	0.0	0.0
07/29/96	31	0.00	0.0	0.00	0.0	0.0
08/05/96	32	0.00	0.0	0.00	0.0	0.0
08/12/96	33	0.00	0.0	0.00	0.0	0.0
08/19/96	34	0.00	0.0	0.00	0.0	0.0
08/26/96	35	0.00	0.0	0.00	0.0	0.0

Fig. 8.4
Operations Plan
Maintenance
(33.15.1)

Site. Enter the supply site code.

Start. Enter the start date for the first calendar week or financial period. The default start date is the system date. If the date you enter is not the Monday of the week or the first day of the period, the system changes it.

Item Number. Enter the end-item number.

Bucket. Enter W to group item quantities into calendar weeks that start on Mondays. Enter P to group quantities into financial periods with a start date that is the first day of the period.

Nbr. Enter the number of the first calendar week or financial period to display. If you enter a bucket number instead of a start date, the system fills in the start date for you. The system also changes the start date to the first day of this week or period if this day is not already the start date.

UM. Enter the unit of measure for viewing and changing item quantities. The default unit of measure is the one from the item master record.

Opening QOH. The screen displays the item's opening on-hand inventory balance.

Sales Fcst. The screen displays the item's consolidated demand from all marketing sites. These global sales forecasts can originate from

either end-item sales forecasts or dependent end-item demand calculated by Family Plan Explosion (33.7.14).

Target Inv. The screen displays the item's consolidated target inventory level for all sites, based on the average weeks-of-coverage factor or on quantities recorded for individual sites.

Prod Due. The screen displays the item's projected production demand for the supply site. The formula is:

(Sales Forecast + Target Inventory) – Previous Week's Projected QOH

For the first week, the previous projected QOH equals the opening QOH. When you change this quantity, the system recalculates global projected quantity on hand and weeks of coverage.

Proj QOH. Initially, projected quantity on hand equals the target inventory level. When you change production due, the system recalculates it as:

[(Previous Week's Projected QOH + Production Due) – Sales Forecast]

Cov. Initially, projected weeks of coverage is the item's average weeks-of-coverage factor. When you change production due, the system recalculates this, using the item's minimum and maximum coverage factors to project inventory shortages (–) and surpluses (+) relative to the average weeks of coverage. An asterisk (*) indicates that projected coverage satisfies the maximum coverage requirement specified in Operations Plan Control File (33.1.24).

Tip

For the first week, the projected QOH is the opening QOH.

Reviewing Site Operations Plans

Use three programs to review plans:

- Operations Plan Inquiry (33.15.2) shows an item's site operations plan much as it appears on the Operations Plan Maintenance (33.15.1) screen.
- Operations Plan Summary Report (33.15.3) shows plans for ranges of items, which you can select by starting plan week, product line, item group, item type, and buyer/planner. You can include only items whose projected coverage is greater or less than the average coverage factor.

- Operations Plan Detail Report (33.15.4) shows plan weeks as vertical rather than horizontal columns.

Changing Line Operations Plans

If you are a master scheduler at a supply site, use Operations Plan Line Maintenance (33.15.6) to view global sales forecasts and target inventory levels and to adjust production due quantities for production lines.

The screen can display item information either by calendar week or by general ledger period. If you normally plan in weeks, do not change production quantities in period view. If you do, the system permanently reassigns all weekly quantities to the first week of the period.

By default, the screen displays production due in item quantities, but you can switch to production hours. By default, the screen displays quantities in the inventory unit of measure, but you can change to any other unit of measure.

To delete a plan for an entire year, choose the plan and press Delete. To delete a plan for part of the year, reset the production due quantities to zero for the affected period.

Operations Plan Line Maintenance									
User Menu Edit Queue Options Help									
					    				
Site: MILAN		Line: 001		Production Line 1			Start: 06/10/96		
Item Number: 0711		Rainbow Ice Cream							
Bucket: W		Nbr: 24	Hrs: no	UM: CS	Opening QOH: 0.0				
Global ---- Site ----- Site ----- Global -----									
Date	Nbr	Sales Fcst	Prod Due	Prod Hrs	Proj QOH	Cov	Shift Hrs		
06/10/96	24	0.00	188.00	0.50	1,500.00	2.0	40		
06/17/96	25	750.00	63.00	0.17	1,250.00	2.0	40		
06/24/96	26	750.00	63.00	0.17	1,000.00	2.0	40		
07/01/96	27	500.00	0.00	0.00	500.00	1.0	40		
07/08/96	28	500.00	0.00	0.00	0.00	0.0	40		
07/15/96	29	0.00	0.00	0.00	0.00	0.0	40		
07/22/96	30	0.00	0.00	0.00	0.00	0.0	40		
07/29/96	31	0.00	0.00	0.00	0.00	0.0	40		
08/05/96	32	0.00	0.00	0.00	0.00	0.0	40		
08/12/96	33	0.00	0.00	0.00	0.00	0.0	40		
08/19/96	34	0.00	0.00	0.00	0.00	0.0	40		
08/26/96	35	0.00	0.00	0.00	0.00	0.0	40		

Fig. 8.5
Operations Plan
Line Maintenance
(33.15.6)

This program is very similar to Operations Plan Maintenance (33.15.1). It includes several additional fields.

See page 87.

Hrs. Enter Yes to update production hours. Enter No to update production quantities.

Prod Due. Production due quantity for the line. You can update this column if Hrs is No. The system calculates line production due from the site production due, based on the percentages defined in Line Allocation Maintenance (33.5.17). When you change production due, the screen recalculates global projected quantity on hand and weeks of coverage.

Prod Hrs. Projected line production hours for the production due quantity. You can update this column if Hrs is Yes. The system calculates projected production hours as:

Line Production Due Quantity ÷ Hourly Line Production Rate

Production rates are defined in Production Line Maintenance (18.1.1).

Shift Hours. Number of weekly shift hours available for production. The system calculates shift hours based on holidays from Holiday Maintenance (36.2.1) and the shift calendar from Shift Maintenance (18.1.22) or shop calendar from Calendar Maintenance (36.2.5).

Reviewing Line Operations Plans

Use Operations Plan Line Inquiry (33.15.7) to view an item's line operations plan.

Changing Line Schedules

Line Utilization Maintenance (33.15.9) helps you balance the operations plan against available line capacity. You can view and change scheduled production in either hours or quantities. As you make changes, the screen recalculates coverage, capacity, and utilization.

The program includes three screens:

- In the selection screen, you specify the production line and first item and planning week to review.
- In the summary screen, you can review and adjust production schedules for multiple items.

- In the detail screen, you can view additional global plan information on the selected item, as well as adjust production.

Selection Screen

Fig. 8.6
Line Utilization
Maintenance
(33.15.9), Selection
Screen

Site. Enter the supply site code.

Production Line. Enter the code of the production line with production quantities you want to view or update.

Item Number. Enter the end-item number, or leave this field blank to choose all items on the line.

UM. Enter the unit of measure for viewing and changing item quantities. The default unit of measure is the one from the item master record.

Start. Enter the start date for the first calendar week or financial period. The default start date is the system date. If the date you enter is not the Monday of the week or the first day of the period, the system changes it.

Week. Enter the number of the planning week.

Production in Weeks/Dates. Enter W to view production by weeks. Enter D to view production by the Monday date of the week. This option determines the headings in the item summary and item detail screens.

Production in Qty/Hrs. Enter Q to update production quantities. Enter H to update production hours. You can change this option in the item summary and item detail screens.

To move to the summary screen, press Go once. To move to the detail screen, press Go twice.

Item Summary Screen

Table 8.1
Navigating in the
Item Summary
Screen

Action	Navigation Commands
Switch between production quantities and production hours	Change Qty/Hrs field
Move between item numbers	Page Up or Page Down
Access scheduled line production fields	Enter from Qty/Hrs field
Choose a group of weeks to display	Next, Previous, or Tab
Save and return to Item Number field	Go or Enter from last displayed line production field
Move between line production fields without saving	Next or Previous
Display columns for next four weeks	Tab
Move to item detail screen	Press Go twice from Item Number field

Fig. 8.7
Line Utilization
Maintenance, Item
Summary Screen

Line Utilization Maintenance							
User Menu Edit Queue Options Help							
Site Production Due - Weeks Of Coverage - Sched Line Produc							
Item Number/Desc	LT	24	25	26	27	28	
0711	0	188.00	63.00	63.00	0.00	0.00	
Rainbow Ice Cream		2.0	2.0	2.0	1.0	0.0	
UM: CS Qty/Hrs: Qty		188.00	63.00	63.00	0.00	0.00	
Site: MILAN	Free Hrs: -	5.61	2.80	40.00	40.00	40.00	
	Available Shift Hours:	40.00	40.00	40.00	40.00	40.00	
Line: 001	Util:	114.0%	93.0%	0.0%	0.0%	0.0%	

Item Number. Enter the end-item number.

Qty/Hrs. Enter Q to update production quantities. Enter H to update production hours. Afterward, press Enter to access the production schedule fields. Or, press Go to move on to the item detail screen.

LT. The screen displays the item-site's lead time (safety, inspection, purchasing, and manufacturing), which the initial plan calculation used to set production release dates.

Site Production Due. The screen displays the item's production due quantity for the supply site. The system calculates production due as:

[(Sales Forecast + Target Inventory) – Previous Week's Projected QOH]

When you change site production due, the system recalculates projected quantity on hand, weeks of coverage, free/available shift hours, and utilization.

Tip

For the first week, the previous projected QOH equals the opening QOH.

Weeks of Coverage. The screen initially displays the item's average weeks-of-coverage factor. When you change production due, the system recalculates this, using the item's minimum and maximum coverage factors to project inventory shortages (–) and surpluses (+) relative to the average weeks of coverage. An asterisk (*) indicates that projected coverage satisfies the maximum coverage requirement specified in Operations Plan Control File (33.1.24).

Sched Line Production. The screen displays production hours or production quantities for the item and line, depending on how you set the Qty/Hrs field. When you change scheduled line production, the screen recalculates free hours, available shift hours, and line utilization.

Site. The screen displays the site code for the production line and item.

Free Hrs. The screen displays the number of shift hours not yet allocated to production. The system calculates free hours as:

(Available Shift Hours – Projected Production Hours)

Available Shift Hours. The screen displays the number of weekly shift hours available for production. The system calculates shift hours based on holidays from Holiday Maintenance (36.2.1) and the shift calendar from Shift Maintenance (18.1.22) or shop calendar from Calendar Maintenance (36.2.5).

Line. The screen displays the production line code.

Util. The screen displays the total line utilization percentage or projected consumption of available production line capacity. The line utilization percentage is:

$$\text{Line Production Due Qty} \div \text{Weekly Line Capacity}$$

Line capacity is:

$$\text{Available Shift Hours} \times \text{Line Production Rate}$$

From the Site Production Due field, press Go or Enter to save your changes and return to the Item Number field.

Item Detail Screen

See page 92.

Navigation in this screen is much the same as in the item summary screen.

Fig. 8.8
Line Utilization
Maintenance, Item
Detail Screen

Item Detail		Rainbow Ice Cream			Qty/Hrs: Qty						
Item Number:	0711	Min Wks:	1	Avg Wks:	2	Max Wks:	3	UM:	CS	LT:	0
Opening QOH:	0.0										
		24	25	26	27	28					
Global Sales Forecast:	0.00	750.00	750.00	500.00	500.00						
Site Production Due:	188.00	63.00	63.00	0.00	0.00						
Sched Line Qty:	188.00	63.00	63.00	0.00	0.00						
Sched Line Hrs:	0.50	0.17	0.17	0.00	0.00						
Projected QOH:	1500.00	1250.00	1000.00	500.00	0.00						
Weeks of Coverage:	2.0	2.0	2.0	1.0	.0						
Item Utilization:	1.3%	0.4%	0.4%	0.0%	0.0%						
Site: MILAN	Free Hrs:	-	5.61	2.80	40.00	40.00	40.00				
	Available Shift Hours:	40.00	40.00	40.00	40.00	40.00					
Line: 001	Util:	114.0%	93.0%	0.0%	0.0%	0.0%					

Item Number. Enter the end-item number.

Qty/Hrs. Enter Q to update production quantities. Enter H to update production hours. Afterward, press Enter to access the production schedule fields. Or, press Go to move on to the item detail screen.

Opening QOH. The item's opening on-hand inventory balance.

Min Wks. The item's minimum weeks-of-coverage factor from Coverage by Date Maintenance (33.5.5), if any, or from Weeks of Coverage Maintenance (33.5.1). The system uses this factor to calculate projected inventory shortages.

Avg Wks. The item's average weeks-of-coverage factor from Coverage by Date Maintenance (33.5.5), if any, or from Weeks of Coverage Maintenance (33.5.1).

Max Wks. The item's maximum weeks-of-coverage factor from Coverage by Date Maintenance (33.5.5), if any, or from Weeks of Coverage Maintenance (33.5.1). The system uses this factor to calculate projected inventory surpluses.

UM. The inventory unit of measure from the item master record.

LT. The item-site's lead time (safety, inspection, purchasing, and manufacturing), which the initial plan calculation used to set production release dates.

Global Sales Forecast. The item's consolidated demand from all marketing sites. These global sales forecasts can originate from either end-item sales forecasts or dependent end-item demand calculated by Family Plan Explosion (33.7.14).

Site Production Due. The item's production due quantity for the supply site. The system calculates production due as:

(Sales Forecast + Target Inventory) – Previous Week's Projected QOH

For the first week, the previous projected QOH equals the opening QOH. When you change site production due, the system recalculates projected quantity on hand, weeks of coverage, free/available shift hours, and utilization.

Sched Line Qty. The item quantity scheduled for the production line for the week or Monday date. The system calculates the line production due using the percentages defined in Line Allocation Maintenance (33.5.17). To update this field, set Qty/Hrs to Qty. When you change the quantity, the system recalculates the global projected quantity on hand, weeks of coverage, item and line utilization, available shift hours and free hours.

Sched Line Hrs. The number of production hours scheduled for the production line for the week or Monday date. The system calculates projected production hours as:

Line Production Due Quantity ÷ Hourly Line Production Rate

Hourly line production rates are defined in Production Line Maintenance (18.1.1). To update this field, set Qty/Hrs to Hrs. When you change the hours, the system recalculates the global projected quantity on hand, weeks of coverage, item and line utilization, available shift hours and free hours.

Projected QOH. The item's global projected on-hand inventory quantity. The system calculates projected quantity on hand as:

(Previous Week's Projected QOH + Production Due) – Sales Forecast

For the first week, the projected QOH is the opening QOH.

Weeks of Coverage. The screen initially displays the item's average weeks-of-coverage factor. When you change production due, the system recalculates this, using the item's minimum and maximum coverage factors to project inventory shortages (–) and surpluses (+) relative to the average weeks of coverage. An asterisk (*) indicates that projected coverage satisfies the maximum coverage requirement specified in Operations Plan Control File (33.1.24).

Item Utilization. The percentage of total available line capacity currently utilized by this item. The system recalculates this if you change Sched Line Qty or Sched Line Hrs.

Site. The site code for the production line and item.

Free Hrs. The number of shift hours not yet allocated to production. The system calculates free hours as:

Available Shift Hours – Projected Production Hours

Available Shift Hours. The number of weekly shift hours available for production. The system calculates shift hours based on holidays from Holiday Maintenance (36.2.1) and the shift calendar from Shift Maintenance (18.1.22) or shop calendar from Calendar Maintenance (36.2.5).

Line. The production line code.

Util. The total line utilization percentage or projected consumption of available production line capacity. The line utilization percentage is:

Line Production Due Qty ÷ Weekly Line Capacity

Line capacity is:

$$\text{Available Shift Hours} \times \text{Line Production Rate}$$

From any scheduled line field, press Go or Enter to save your changes and return to the item summary screen.

Reviewing Line Schedules

Line Utilization Summary Report (33.15.10) shows line scheduling information for a range of sites and production lines. You can print production due in either item quantities or line production hours.

Reviewing Projected Inventory Coverage

Two reports show data on projected inventory coverage.

- Coverage Detail Report (33.15.19) has three columns that group operations plan data by week. Each column shows global sales forecasts, site production due, global projected quantity on hand, and global weeks of coverage.
- Coverage Summary Report (33.15.20) has three columns that group operations plan data by category. Each column shows global sales forecasts, site production due, and global weeks of coverage.

Both reports show up to three weeks of data plus opening quantity on hand for each item, and both sort and total by product line, item group, and item.

Reviewing Site Utilization

Site Utilization Inquiry (33.15.12) shows line utilization for one or all production lines in a site.

Reviewing Production Labor Hours

Production Labor Inquiry (33.15.11) shows projected labor hours required to execute scheduled line production. This inquiry calculates total site labor hours based on the run crew size specified in Production Line Maintenance (18.1.1).

CHAPTER 9

Transfer of Production Demands

This chapter describes how to transfer operations plan production demands to work orders, purchase requisitions, and repetitive schedules. It also describes activities required for subsequent processing by MRP/DRP.

Introduction **100**

Exploding the Operations Plan into Orders **100**

Approving Orders to Other Modules **103**

Balancing Target Inventory Levels and MRP **106**

The screenshot displays a software window titled "Routing Maintenance (Main Screen)". It contains a form with the following fields and values:


Routing Code: 10-15000		NORAD (75) CDR INC.	
Operation:	20		
Standard Operation			
Work Center	1030		INSPECTION, ALL SITES
Machines			
Description	INSPEC PER PROG-005		
Machines per Op	1		Attention: P...
Overlap Units	1		
Queue Time	1.0		
Wait Time	0.0		
Setup Time	0.0		
Route by Production B...			

Introduction

The operations plan is the equivalent of a master production schedule. Once you are satisfied with the plan, you can transfer control of the production demands directly into the processing cycles of other modules in MFG/PRO eB. You can approve production demands as work orders, repetitive schedules, or purchase requisitions. This saves time, minimizes downstream processing, and decreases the likelihood of errors.

Figure 9.1 shows the work flow for transferring the operations plan.

Fig. 9.1
Transfer Work
Flow



Exploding the Operations Plan into Orders

You must explode the production demands calculated in the operations plan to the supply sites that will manufacture or purchase the items.

Figure 9.2 shows the explosion calculation. For most items, the explosion creates firm planned orders for the production due quantities in the operations plan.




Fig. 9.2
Explosion
Calculation

For co-product and by-product items, the explosion creates batch work orders (Status B) for the base process. The explosion does not create work orders for co-products or by-products. When you change the work order status from B to F, the system generates firm planned work order sets for the co-products and by-products associated with the base process.

Outside of the Enterprise Operations Plan module, these orders have the status firm planned. The system distinguishes operations plan orders from other orders by a special remark (OpsPlan). In form and function, these orders resemble master schedule orders.

However, within the Enterprise Operations Plan module, these orders behave more like MRP planned orders—that is, subsequent operations plan explosions will still add, delete, or change them.

The explosion assigns the orders to the supply sites designated in the item source matrix. It sets order due dates to the Monday of the week. It calculates release dates by offsetting item lead times from the due date.

Note The explosion transfers information only to sites in connected MFG/PRO eB databases. To distribute orders to non-MFG/PRO eB databases, send the output to a file. You can then translate this file to Open Application Group (OAG) or Application Linking and Embedding (ALE) standards.

Running Operations Plan Explosion

Use Operations Plan Explosion (33.15.13) to explode the operations plan. Whenever you change the operations plan, rerun the explosion to change the original records and create new firm planned orders. You can rerun the explosion as often as necessary. Subsequent explosions ignore previously approved items.

To review or change orders generated by the explosion, use the Work Orders module. For base process items, run Multiple WO Status Change (16.8) to change the order status from batch (B) to firm planned (F). This generates the firm planned orders for co-products and by-products associated with the base process. You must change the work order status before you can approve these orders in the Enterprise Operations Plan module.

Exploded orders also update projected quantity on hand, planned orders due, and planned order release quantities in MRP records. To review MRP records after an explosion, use one of the inquiries or reports in the Material Requirements Plan module.

Fig. 9.3
Operations Plan
Explosion
(33.15.13)

Item Number/To. Enter the item number range.

Site/To. Enter the site range.

Effective/To. Enter the effective date range. When you specify a non-Monday start date or a non-Sunday end date, the system changes it.

Product Line. If you specify a value, the system processes only items belonging to this product line.

Item Group. If you specify a value, the system processes only items belonging to this item group.

Buyer/Planner. If you specify a value, the system processes only items assigned to this person.

Use Planning Time Fence. Enter Yes to prevent the explosion from recalculating production quantities due within the item-site time fence period. This setting protects the master schedule against last-minute

orders with a cumulative lead time that exceeds the available production time. Enter No to permit recalculations.

Regenerate Firm Planned Orders. Enter Yes to regenerate operations plan orders created by earlier explosions. Enter No to run a net-change explosion. If you run the explosion and later change production due quantities in the operations plan, the system automatically updates production quantities on the corresponding orders, regardless of how you set this option. The system also updates the orders if you change the order due date or release date. However, the system does not update orders if you change other information that affects them, such as item lead times. Whenever you make changes like these, enter Yes.

Output. Enter the output for the report—terminal, printer, or ASCII file name.

Batch ID. If you enter a batch ID, the system does not run this process immediately. It puts the request in a queue for batch processing.

Approving Orders to Other Modules

Once the production demands are exploded to the supply sites, they are almost ready for manufacturing and purchasing.

The last step is for each supply site to approve its exploded work orders. Approval freezes order quantities against subsequent replanning by operations planning. Approval also converts the demands to the correct form for subsequent manufacturing or purchasing activity—that is, to firm planned work orders, repetitive schedules, or purchase requisitions.

Many companies have a management authorization process for production demands. Manufacturing and purchasing can process these demands only after management has reviewed and approved them. Generally, you approve orders with due dates that are inside the item time fence.

In multi-database environments, local schedulers approve orders from the central planning database. The system automatically switches to the local planning database.

▶ See *User Guide Volume 9: Manager Functions* for security details.

Important Approval is irreversible. Once you approve an operations plan order, you cannot change or re-explode it. To restrict unauthorized access, set up password security.

Approval converts the operations plan firm planned orders into one of three formats:

▶ See *User Guide Volume 3: Manufacturing* for details on work orders and repetitive.

- Firm planned work orders. The approval updates the existing exploded firm planned orders to prevent subsequent plan explosions from changing them. It also changes the work order remark to Ops Plan Approved.
- Repetitive schedules. The approval places each week's production quantities into a repetitive schedule due on the Monday of the week. You must then manually redistribute this quantity across the rest of the week.

Repetitive schedule approvals overwrite existing repetitive schedule quantities for the Mondays of the weeks. However, they do not overwrite quantities for the remaining days of the weeks.

▶ See *User Guide Volume 2: Distribution* for details on purchase requisitions.

- Purchase requisitions. The approval generates purchase requisitions, which you can later convert to purchase orders.

Running Operations Plan Approval

Use Operations Plan Approval (33.15.14) to approve individual orders or items in a chosen range. There are two frames:

- In the first, choose groups of orders for approval.
- In the second, modify the selection for individual orders.

After approval, adjust due dates, release dates, quantities, or other information with the appropriate maintenance programs in the Work Orders, Repetitive, or Purchasing module.

Fig. 9.4
Operations Plan
Approval
(33.15.14),
Selection Criteria

Item Number/To. Enter the item number range.

Site/To. Enter the site range.

Production Line. Enter the production line range.

Start/To. Enter the effective date range. When you specify a non-Monday start date or a non-Sunday end date, the system changes it. Enter the effective date range for the load. When you specify a non-Monday start date or a non-Sunday end date, the system changes it. To load inventory quantities for a planning week, you must set the effective date to the Monday of the previous week.

Buyer/Planner. If you specify a value, the system processes only items assigned to this person.

Default Approve. Enter Yes to approve most or all orders. You can exclude individual orders in the second approval screen. Enter No to choose orders manually.

Include Zero Requirements. Enter No to exclude zero-quantity work orders. Enter Yes to include them.

Ignore Pur/Mfg Code. Enter No to approve orders only to formats appropriate for the item master purchase/manufacture code, and to choose only orders appropriate for the approval method. Enter Yes to approve all orders.


Use Planning Time Fence. Enter Yes to choose only orders due in the immediate future. Enter No to choose all orders regardless of due date.

Tip
The ending inventory of the prior week becomes the beginning projected available inventory for the current planning week.

Method. Enter 1 to approve operations plan orders as firm planned work orders, 2 to approve orders as repetitive schedules, or 3 to approve orders as purchase requisitions. To prevent the system from approving orders to formats inappropriate for their item purchase/manufacture code, set Ignore Pur/Mfg Code to No.

Press Go to proceed to the order selection screen.

Fig. 9.5
Operations Plan
Approval
(33.15.14), Order
Selection



Operations Plan Approval					
User Menu Edit Queue Options Help					
Item	Site	Line	Due Date	Qty	Approve
0711	MILAN	001	06/10/96	16,875.0	yes
0711	MILAN	001	06/17/96	9,938.0	yes
0711	MILAN	001	06/24/96	7,313.0	yes
0711	MILAN	002	06/10/96	5,625.0	yes
0711	MILAN	002	06/17/96	3,313.0	yes
0711	MILAN	002	06/24/96	2,438.0	yes

Running Operations Plan Batch Approval

Use Operations Plan Batch Approval (33.15.15) to approve ranges of orders in batch. This program is similar to Operations Plan Approval, but only one frame displays and it includes an Output and Batch ID field.

Balancing Target Inventory Levels and MRP

Before you run MRP/DRP, you must compensate for a gap between operations planning and MRP/DRP processing—target inventory. If you do not, MRP/DRP will later generate erroneous order cancellation messages in supply sites.

Operations planning generates orders for both sales forecasts and target inventory. But MRP/DRP generates orders only for sales forecasts. When it encounters target inventory orders, it cannot link them back to specific sales forecasts.

To prevent the error messages, you must usually run Balance Target Inventory and MRP (33.15.17) after you explode the operations plan. Run this utility for all marketing sites, in all MFG/PRO eB databases that run MRP/DRP.

Note You do not need to run the utility for items with an average weeks-of-coverage factor of zero. There is always a one-to-one correspondence between each week's target inventory levels and sales forecasts.

The utility generates seasonal build demands for the marketing site. The seasonal build quantity matches the target inventory level. The combined sales forecast plus seasonal build equals the MRP planned orders for the operations planning production demands.

After running the utility, you can use Seasonal Build Maintenance (22.9) to adjust seasonal build quantities or other information.

Fig. 9.6
Balance Target
Inventory and MRP
(33.15.17)

Item Number/To. Enter the item number range.

Site/To. Enter the site range.

Effective/To. Enter the effective date range. When you specify a non-Monday start date or a non-Sunday end date, the system changes it.

Product Line. If you specify a value, the system processes only items belonging to this product line.

Item Group. If you specify a value, the system processes only items belonging to this item group.

Buyer/Planner. If you specify a value, the system processes only items assigned to this person.

Update Changes Only. Enter Yes to prevent the utility from duplicating previously created seasonal build quantities. Enter No only if you must re-create seasonal build quantities.

Output. Enter the output for the report—terminal, printer, or ASCII file name.

Tip
Specify Yes if you rerun the utility for a planning period.

Batch ID. If you enter a batch ID, the system does not run this process immediately. It puts the request in a queue for batch processing.

CHAPTER 10

Performance Measurement

Operations Plan includes programs that report on actual vs planned sales, inventory, and production performance.



param91.p 14.13.2 Routing Maintenance (Main Screen)

Routing Code:	10-15000	NONAD (75) COOLING
Operation:	20	
Standard Operation	10.00	INSPECTION, ALL SITES
Work Center		
Machine		
Description:	INSPEC PER PROC-005	
Machines per Op:	1	Milestone: 1
Overlap Units:	1	
Queue Time:	1.0	
Wait Time:	0.0	
Setup Time:	0.0	
Route by Production	Build	

At the departmental level, sales and marketing managers want to know how accurately they forecasted sales. Inventory managers want to know whether actual balances were in line with target levels. Production managers want to know whether actual production met the projected requirement. At the corporate level, master schedulers want to see global and site-level family and end-item sales, inventory, and production.

After you have rolled up end-item changes to the family plan, you can use several inquiries and reports to track performance in these areas.

Reviewing Actual vs Planned Sales

- Sales Data Inquiry (33.19.1) shows sales forecasts, actual sales, and variances for individual item-sites. You can use this inquiry for both family items and end items. You can view quantities by week or fiscal period and in any item unit of measure.
- Sales Data Report (33.19.2) shows the same information for ranges of items, sites, and planning periods.

Reviewing Actual vs Planned Inventory

- Inventory Data Inquiry (33.19.4) shows target inventory, actual quantity on hand, and variances for individual item-sites. You can use this inquiry for both family items and end items. You can view quantities by week or fiscal period and in any item unit of measure.
- Inventory Data Report (33.19.5) shows the same information for ranges of items, sites, and planning periods.

Reviewing Actual vs Planned Production

- Production Data Inquiry (33.19.7) shows production due, actual production, and variances for individual item-sites. You can use this inquiry for both family items and end items. You can view quantities by week or fiscal period and in any item unit of measure.
- Production Data Report (33.19.8) shows the same information for ranges of items, sites, and planning periods.

Reviewing Global Actual vs Planned Performance

- Performance Inquiry (33.19.13) shows actual, planned, and variance quantities for sales, inventory, and production. You can use this inquiry for both family items and end items. You can view quantities by week or fiscal period, and in any item unit of measure.
- Performance Report (33.19.14) is similar but shows information for ranges of items, sites, and planning periods.

Simulation Planning


This chapter describes activities required to generate and maintain simulation plans for family items and end items.

Introduction **114**

Creating Simulation Plans **114**

Maintaining Simulation Plans **116**

Copying Simulation Plans to Active Plans **118**




Introduction

During the plan review process, it can be helpful to experiment with the effects of changing production due quantities. You can create simulations of both family and operations plans.

Figure 11.1 shows the simulation planning work flow.

Fig. 11.1
Simulation
Planning Work
Flow



Creating Simulation Plans

To create simulation plans from an active family plan, operations plan, or another simulation plan, use Copy Plan to Simulation (33.17.1). This program copies sales forecasts, target inventory levels, and production due quantities. However, it does not copy projected quantity on hand or weeks of coverage. When you change quantities in the simulation plan maintenance programs, the system recalculates these.

Note You cannot change weeks of coverage or other plan calculation factors in full-scale simulation mode. However, you can save the active plan to a simulation file, change the factors and recalculate the plan. Then, if necessary, copy the stored plan back. Obviously, if you do this, you must institute appropriate procedural controls.

You can generate an unlimited number of simulation plans.

The screenshot shows a software window titled "Copy Plan To Simulation". It features a menu bar with "User Menu", "Edit", "Queue", "Options", and "Help". Below the menu bar is a toolbar with icons for file operations. The main area contains several input fields: "Plan ID:" with the text "SIM", "Item Number:" with "0711", "Year:" with "1996", "To:" with "0711", and another "To:" with "1996". There are also empty fields for "Buyer/Planner:", "Product Line:", "Item Group:", and "Item Type:". A checkbox for "Overwrite Existing Plan:" is checked, showing "no". At the bottom right, there are labels for "Output:" and "Batch ID:".

Fig. 11.2
Copy Plan to
Simulation
(33.17.1)

Plan ID. Enter a code (maximum eight characters) to identify the simulation plan.

Item Number/To. Enter the item number range.

Year/To. Enter a maximum range of three calendar years, starting with the current year.

Buyer/Planner. If you specify a value, the system processes only items assigned to this person.

Product Line. If you specify a value, the system processes only items belonging to this product line.

Item Group. If you specify a value, the system processes only items belonging to this item group.

Item Type. If you specify a value, the system processes only items belonging to this item type.

Overwrite Existing Plan. Enter Yes to overwrite previously generated simulation plan records for the selected items, plan years, and so on. Enter No to preserve the previous plan records in the new simulation plan.

Output. Enter the output for the report—terminal, printer, or ASCII file name.

Batch ID. If you enter a batch ID, the system does not run this process immediately. It puts the request in a queue for batch processing.

Maintaining Simulation Plans

Like operations plans, you can manipulate simulation plans at the site and production line levels.

Changing Site Simulation Plans

To view the plan and simulate changes to production due quantities, use Simulation Plan Maintenance (33.17.13). To help you make more informed decisions, the screen displays the global sales forecasts and global target inventory levels. As you change quantities, the system recalculates projected quantity on hand and projected weeks of coverage.

You can also use Simulation Plan Maintenance to delete a simulation plan, either for an entire year, or for only specific periods within the year. For example, you may have to do this if an item becomes obsolete.

Fig. 11.3
Simulation Plan
Maintenance
(33.17.13)

Simulation Plan Maintenance						
User Menu Edit Queue Options Help						
Plan ID: SIM		Site: MILAN		Milan, Italy		Start: 06/10/96
Item Number: 0711				Rainbow Ice Cream		
Bucket: W		Nbr: 24		UM: CS		Opening QOH: 0.0
-----Global----- Global----- Site ----- Global						
Date	Nbr	Sales Fcst	Target Inv	Prod Due	Proj QOH	Cov
06/10/96	24	2000.00	4,000.0	750.00	-500.0	0.0 -
06/17/96	25	3250.00	4,250.0	250.00	-3,250.0	0.0 -
06/24/96	26	3750.00	4,500.0	250.00	-6,500.0	0.0 -
07/01/96	27	4000.00	4,500.0	0.00	-10,500.0	0.0 -
07/08/96	28	500.00	0.0	0.00	-11,000.0	0.0 -
07/15/96	29	0.00	0.0	0.00	-11,000.0	0.0 -
07/22/96	30	0.00	0.0	0.00	-11,000.0	0.0 -
07/29/96	31	0.00	0.0	0.00	-11,000.0	0.0 -
08/05/96	32	0.00	0.0	0.00	-11,000.0	0.0 -
08/12/96	33	0.00	0.0	0.00	-11,000.0	0.0 -
08/19/96	34	0.00	0.0	0.00	-11,000.0	0.0 -
08/26/96	35	0.00	0.0	0.00	-11,000.0	0.0 -

See “Changing Site Operations Plans” on page 86.

The fields in Simulation Plan Maintenance are identical to those in Operations Plan Maintenance.


Use two programs to view simulated plan information:

- Simulation Plan Inquiry (33.17.14) shows an item’s site simulation plan much as it appears on the Simulation Plan Maintenance (33.17.13) screen.

- Simulation Summary Report (33.17.6) shows plans for ranges of items, which you can choose by starting plan week, product line, item group, item type, and buyer/planner. You can limit the report to items whose projected coverage is greater or less than the average coverage factor.

Changing Line Simulation Plans

Use Simulation Line Plan Maintenance (33.17.16) to view the plan and simulate changes to production due quantities at the production line level.



Simulation Line Plan Maintenance									
User Menu Edit Queue Options Help									
Plan ID: SIM Site: MILAN Line: 001 Start: 06/10/96									
Item Number: 0711 Rainbow Ice Cream									
Bucket: W Nbr: 24 Hrs: no UM: CS QOH: 0.0									
Global ---- Site ---- Site ---- Global ----									
Date	Nbr	Sales Fcst	Prod Due	Prod Hrs	Proj QOH	Cov	Shift Hrs		
06/10/96	24	2000.00	100.00	0.50	-500.00	0.0	-	40	
06/17/96	25	3250.00	63.00	0.17	-3,250.00	0.0	-	40	
06/24/96	26	3750.00	63.00	0.17	-6,500.00	0.0	-	40	
07/01/96	27	4000.00	0.00	0.00	-10,500.00	0.0	-	40	
07/08/96	28	500.00	0.00	0.00	-11,000.00	0.0	-	40	
07/15/96	29	0.00	0.00	0.00	-11,000.00	0.0	-	40	
07/22/96	30	0.00	0.00	0.00	-11,000.00	0.0	-	40	
07/29/96	31	0.00	0.00	0.00	-11,000.00	0.0	-	40	
08/05/96	32	0.00	0.00	0.00	-11,000.00	0.0	-	40	
08/12/96	33	0.00	0.00	0.00	-11,000.00	0.0	-	40	
08/19/96	34	0.00	0.00	0.00	-11,000.00	0.0	-	40	
08/26/96	35	0.00	0.00	0.00	-11,000.00	0.0	-	40	

Fig. 11.4
Simulation Line
Plan Maintenance
(33.17.16)

The fields in Simulation Line Plan Maintenance are identical to those in Operations Plan Line Maintenance.

Use Simulation Line Plan Inquiry (33.17.17) to display an item's line simulation plan.

See "Changing Line Operations Plans" on page 89.

Changing Simulation Line Schedules

Simulation Line Util Maintenance (33.17.19) simulates balancing the operations plan against available line capacity. You can view and change scheduled production in either hours or quantities. As you make changes, the screen recalculates coverage, capacity, and utilization.

Fig. 11.5
Simulation Line
Util Maintenance
(33.17.19)

♦ See “Changing Line Schedules” on page 90.

The multiple screens and fields in the program are identical to those in Line Utilization Maintenance.

Simulation Line Util Report (33.17.20) shows line scheduling information for a range of sites and production lines. You can print production due in either item quantities or line production hours.

Copying Simulation Plans to Active Plans

When you are satisfied with a simulation plan, use Copy Simulation to Plan (33.17.3) to copy the plan back over the active family plan or operations plan.

Note Be careful not to copy the simulation plan prematurely or in error. The system does not keep a backup copy of the old active plan.

Copy Simulation to Plan

User Menu Edit Queue Options Help

Plan ID: SIM

Item Number: 0711 To: 0711

Year: 1996 To: 1996

Buyer/Planner:

Product Line:

Item Group:

Item Type:

Effective Date: 06/14/96

Overwrite Existing Plan: ☒ yes

Output:

Batch ID:

Fig. 11.6
Copy Simulation to
Plan (33.17.3)

Plan ID. Enter a code (maximum eight characters) to identify the simulation plan.

Item Number/To. Enter the item number range.

Year/To. Enter a maximum range of three calendar years, starting with the current year.

Buyer/Planner. If you specify a value, the system processes only items assigned to this person.

Product Line. If you specify a value, the system processes only items belonging to this product line.

Item Group. If you specify a value, the system processes only items belonging to this item group.

Item Type. If you specify a value, the system processes only items belonging to this item type.

Overwrite Existing Plan. Enter Yes to overwrite previously generated simulation plan records for the selected items, plan years, and so on. Enter No to preserve the previous plan records in the new simulation plan.

Output. Enter the output for the report—terminal, printer, or ASCII file name.

Batch ID. If you enter a batch ID, the system does not run this process immediately. It puts the request in a queue for batch processing.

CHAPTER 12

System Administration

This chapter describes general steps for updating records and preserving database space.

Introduction **122**

Maintaining Static Data **122**

Deleting Old Data **123**

Recalculating Summary Records **124**

Routing Code: 10-15000 WORK CENTER: 10-15000

Operation: 20 INSPEC PER PROC-005

Standard Operation: 10.00 Inspection: ALL SITE

Machine: Milestone: 10.00

Description: Setup Time: 0.0

Machines per Op: 1 Run by: Production, Build

Overlap Units: 1 Milestone: 10.00

Queue Time: 1.0 Milestone: 10.00

Wait Time: 0.0 Milestone: 10.00

Introduction

Periodically, you should perform certain tasks to update records and to preserve database space.

- When you change certain records in other MFG/PRO eB modules, or whenever certain conditions change in your company, you must update operations planning master data.
- Typically at year-end, you should delete and optionally archive obsolete plan records.
- If inconsistencies develop between global and site-level quantities, you must run a utility program to correct the problem.

This chapter outlines these procedures.

Maintaining Static Data

When your company changes item numbers, intersite sourcing relationships, and so on, you must update records in the Enterprise Ops Plan module. Table 12.1 lists events that require such updates.

Table 12.1
Events Requiring
Operations Plan
Record Updates

Event	Update Operations Plan Records in
Item numbers change	Family Hierarchy Change (33.3.6)
	Family Item Cost Maintenance (33.3.13)
	Weeks of Coverage Maintenance (33.5.1)
	Coverage by Date Maintenance (33.5.5)
	Source Matrix Maintenance (33.5.13)
	Line Allocation Maintenance (33.5.17)
	Item Pallet Maintenance (33.5.23)
Item records are added or deleted	Family Hierarchy Maintenance (33.3.1)
	Family Item Cost Maintenance (33.3.13)
	Weeks of Coverage Maintenance (33.5.1)
	Coverage by Date Maintenance (33.5.5)
	Source Matrix Maintenance (33.5.13)
	Line Allocation Maintenance (33.5.17)
	Item Pallet Maintenance (33.5.23)

Event	Update Operations Plan Records in
Target inventory levels change	Weeks of Coverage Maintenance (33.5.1) Coverage by Date Maintenance (33.5.5)
Intersite sourcing relationships change	Source Matrix Maintenance (33.5.13)
Intrasite production line relationships change	Line Allocation Maintenance (33.5.17)

At year-end, additional activities are required:

- Verify that records in Family Hierarchy Maintenance (33.3.1) and Source Matrix Maintenance (33.5.13) are still valid for the remainder of your planning horizon. Update the end dates as necessary.
- Rerun Calendar Cross-Reference Build (33.1.4) for the remainder of your planning horizon (up to three years).

▶ See Chapter 3, “Required Implementation,” on page 21 and Chapter 4, “Family Data Implementation,” on page 31.

Deleting Old Data

The system does not automatically delete old operations planning records. To preserve disk space, you should periodically remove outdated records.

Data	Program
Family hierarchies	Family Hierarchy Delete/Archive (33.3.23)
Family plans	Operations Plan Delete/Archive (33.15.23)
Data loaded into Item-Site Data Maintenance (33.13.3)	Item-Site Data Consolidation (33.13.6), Delete Item-Site Load Records option
Operations plans	Operations Plan Delete/Archive (33.15.23)
Work orders generated by Operations Plan Explosion (33.15.13)	Work Order Delete/Archive (16.23)
Simulation plans	Simulation Delete/Archive (33.17.23)

Table 12.2
Records To Be
Periodically
Deleted

Do not remove records until all processing is complete for the planning period. When selecting data to delete/archive, consider how you want to manage restorations.

Example If you delete/archive an entire year’s history, you must reload the entire file even if you only need data for a day or week.

Establish procedures to handle archive files. Keep a separate record of the file name and contents because there is no label within the file. The ASCII file name identifies only the module and the file creation date. Then, if you later reload the data, you will know which file to load from.

Note Set up security for delete/archive programs. The system does not maintain an audit trail of deleted records.

Delete. Enter Yes to delete the selected records. Enter No to print a report of records to delete. Before deleting records, run this program with Delete set to No. Review the report, then rerun the program with Delete set to Yes.


Archive. Enter Yes to copy deleted records to a disk file to be stored off-line. If you ever need to restore data, copy the file back to disk. Then, use Archive File Reload (36.16.5) to reload the file.

Archive File. The Archive option generates an ASCII file called xxYYMMDD.hst, where xx is the module code and YYMMDD is the delete/archive date. If you already ran the delete/archive for this date, the system appends to the existing file.

Recalculating Summary Records

After a database crash or other such event, the system can develop inconsistencies between an item's site-level and global quantities. If this happens, use Recalculate Summary Records (33.25.1) to rebuild family plan and operations plan summary records.

Fig. 12.1
Recalculate
Summary Records
(33.25.1)




CHAPTER 13

Operations Plan Examples

This chapter gives two examples: a family plan example illustrating consolidation, explosion, and rollup calculations; and an operations plan example illustrating supply site and production line calculations.

Family Plan Example **126**

Operations Plan Example **133**



Routing Maintenance (Date Based)

Routing Code:	10-15000	NONAD(75) CDB INC
Operation:	20	
Standard Operation		
Work Center	1030	INSPECTION, ALL SITES
Machine		
Description	INSPEC PER PROX-005	
Machines per Op	1	Milestone
Overlap Units	1	
Queue Time	1.0	
Wait Time	0.0	
Setup Time	0.0	
Ready for Production	By M/C Prod	

Family Plan Example

This example illustrates consolidation, explosion, and rollup calculations for a family plan. Calculations are shown by planning week.

Global Consolidation

For each week with sales forecasts, Global Consolidation (33.7.1) calculates global forecasts by totaling family forecasts from marketing sites. Family forecasts can either be recorded directly or rolled up from end-item forecasts.

Table 13.1
Global Forecasts
Calculations

Week	Site A Forecasts	Site B Forecasts	Global Forecasts
1	0	0	0
2	100	150	250
3	200	300	500
4	100	200	300
5	150	250	400
6	150	150	300
7	150	150	300
8	175	225	400
9	200	225	425
10	0	0	0
11	0	0	0
12	0	0	0

The consolidation uses the item's average weeks-of-coverage factor (2.0) to calculate global target inventory levels. Therefore, each week's global target inventory equals the sum of the next two weeks of sales forecasts.

Table 13.2
Global Target
Inventory
Calculations

Week	Global Forecasts	Global Target Inventory Levels
1	0	$250 + 500 = 750$
2	250	$500 + 300 = 800$
3	500	$300 + 400 = 700$
4	300	$400 + 300 = 700$

Week	Global Forecasts	Global Target Inventory Levels
5	400	$300 + 300 = 600$
6	300	$300 + 400 = 700$
7	300	$400 + 425 = 825$
8	400	$425 + 0 = 425$
9	425	0
10	0	0
11	0	0
12	0	0

The consolidation calculates global production due as:

$$(\text{Sales Forecast} + \text{Target Inventory}) - \text{Previous Projected Quantity on Hand}.$$

For family-level planning, the initial opening quantity on hand is always zero. For subsequent weeks, the previous week's quantity on hand equals the target inventory level.

Week	Sales Forecast	Target Inventory	Projected QOH	Gross Production Due
1	0	750	0	$(0 + 750) - 0 = 750$
2	250	800	750	$(250 + 800) - 750 = 300$
3	500	700	800	$(500 + 700) - 800 = 400$
4	300	700	700	$(300 + 700) - 700 = 300$
5	400	600	700	$(400 + 600) - 700 = 300$
6	300	700	600	$(300 + 700) - 600 = 400$
7	300	825	700	$(300 + 825) - 700 = 425$
8	400	425	825	$(400 + 425) - 825 = 0$
9	425	0	425	$(425 + 0) - 425 = 0$
10	0	0	0	0
11	0	0	0	0
12	0	0	0	0

Table 13.3
Gross Production
Due Calculations

The consolidation initially calculates projected quantity on hand to equal the target inventory level. However, if you change production due, the system recalculates it as:

$$\text{Previous Week's Projected QOH} + \text{Production Due} - \text{Sales Forecast}$$

If production due for the first week increases from 750 to 900. The system recalculates quantities as follows.

Table 13.4
Projected
Quantities on Hand
Calculations

Week	Previous QOH	Production Due	Sales Forecast	Projected QOH
1	0	900	0	$(0 + 900) - 0 = 900$
2	900	300	250	$(900 + 300) - 250 = 950$
3	950	400	500	$(950 + 400) - 500 = 850$
4	850	300	300	$(850 + 300) - 300 = 850$
5	850	300	400	$(850 + 300) - 400 = 750$
6	750	400	300	$(750 + 400) - 300 = 850$
7	850	425	300	$(850 + 425) - 300 = 975$
8	975	0	400	$(975 + 0) - 400 = 575$
9	575	0	425	$(575 + 0) - 425 = 150$
10	150	0	0	$(150 + 0) - 0 = 150$
11	150	0	0	$(150 + 0) - 0 = 150$
12	150	0	0	$(150 + 0) - 0 = 150$

The consolidation initially calculates projected weeks of coverage as the family item's average weeks-of-coverage factor. But the system recalculates it when you change production due.

For each week, the system subtracts the forecast for each upcoming week, until it encounters a week for which the on-hand quantity is insufficient to cover the forecast. It then divides the remaining inventory by the sales forecast for that week. Finally, it calculates the weeks of coverage by totaling the number of complete weeks and the decimal for the partial week.

Table 13.5
Projected Weeks of
Coverage
Calculations

Week	Projected QOH	Sales Forecast	Projected Weeks of Coverage
1	900	0	$900 - 250 = 650$ $650 - 500 = 150$ $150 \div 300 = 0.5$ 2.5 weeks
2	950	250	$950 - 500 = 450$ $450 - 300 = 150$ $150 \div 400 = 0.375$ ~ 2.4 weeks

Week	Projected QOH	Sales Forecast	Projected Weeks of Coverage
3	850	500	$850 - 300 = 550$ $550 - 400 = 150$ $150 \div 300 = 0.5$ 2.5 weeks
4	850	300	$850 - 400 = 450$ $450 - 300 = 150$ $150 \div 300 = 0.5$ 2.5 weeks
5	750	400	$750 - 300 = 450$ $450 - 300 = 150$ $150 \div 400 = 0.375$ ~ 2.4 weeks
6	850	300	$850 - 300 = 550$ $550 - 400 = 150$ $150 \div 425 = 0.353$ ~ 2.4 weeks
7	975	300	*
8	575	400	*
9	150	425	*
10	150	0	*
11	150	0	*
12	150	0	*

* Maximum weeks of coverage specified in Operations Plan Control File (33.1.24).

Family Plan Explosion

Family Plan Explosion (33.7.14) calculates dependent end-item demands for family item gross production due quantities. To do this, it uses either the planned or calculated forecast percentage for the subfamily, which you specify when you run the explosion. Once you select this percentage, however, the calculations are the same.

Table 13.6 shows gross production due if 25% of the forecast is for subfamily A and the remaining 75% for subfamily B.

Table 13.6
Gross Production
Calculations

Week	Gross Production	Gross Production Subfamily A	Gross Production Subfamily B
1	900	$900 \times 25\% = 225$	$900 \times 75\% = 675$
2	300	$300 \times 25\% = 75$	$300 \times 75\% = 225$
3	400	$400 \times 25\% = 100$	$400 \times 75\% = 300$
4	300	$300 \times 25\% = 75$	$300 \times 75\% = 225$
5	300	$300 \times 25\% = 75$	$300 \times 75\% = 225$
6	400	$400 \times 25\% = 100$	$400 \times 75\% = 300$
7	425	$425 \times 25\% = 106.25$	$425 \times 75\% = 318.75$
8	0	0	0
9	0	0	0
10	0	0	0
11	0	0	0
12	0	0	0

Whenever units of measure vary between family and subfamily levels, the explosion converts quantities to the unit for the lower level. In this example, the family unit is metric tons, and the end-item unit is cases. A case weighs 36 kilos, so the unit-of-measure conversion factors are 1 CS = 0.036 TN and 1 TN = 27.78 CS.

Table 13.7
Gross Production
Calculations for
Subfamily A

Week	Family Gross Production (TN)	Gross Production Subfamily A (CS)
1	225	$225 \times 27.778 = \sim 6,250$
2	75	$75 \times 27.778 = \sim 2,083$
3	100	$100 \times 27.778 = \sim 2,778$
4	75	$75 \times 27.778 = \sim 2,083$
5	75	$75 \times 27.778 = \sim 2,083$
6	100	$100 \times 27.778 = \sim 2,778$
7	106.25	$106.25 \times 27.778 = \sim 2,951$
8	0	0
9	0	0
10	0	0
11	0	0
12	0	0

Week	Family Gross Production (TN)	Gross Production Subfamily B (CS)
1	675	$675 \times 27.778 = \sim 18,750$
2	225	$225 \times 27.778 = \sim 6,250$
3	300	$300 \times 27.778 = \sim 8,333$
4	225	$225 \times 27.778 = \sim 6,250$
5	225	$225 \times 27.778 = \sim 6,250$
6	300	$300 \times 27.778 = \sim 8,333$
7	318.75	$318.75 \times 27.778 = \sim 8,854$
8	0	0
9	0	0
10	0	0
11	0	0
12	0	0

Table 13.8
Gross Production
Calculations for
Subfamily B

The system stores dependent end-item demands as sales forecasts. Source Matrix Explosion (33.13.8) uses these forecasts to calculate the end-item operations plan.

Family Plan Rollup

Family Plan Rollup (33.7.13) updates the family plan when you change end-item information—for example, when you change production due quantities. In this example, production due for the first week increases from 6,250 to 6,500 cases.

The rollup works much like Family Plan Explosion (33.7.14), only in reverse. It starts by converting the end-item quantity back to the family item unit of measure.

Table 13.9
Family Plan
Explosion
Calculations for
Subfamily A

Week	End Item Production Due (CS)	Gross Production Subfamily A (TN)
1	6,500	$6,500 \div 27.778 = \sim 234$
2	2,083	$2,083 \div 27.778 = \sim 75$
3	2,278	$2,778 \div 27.778 = \sim 100$
4	2,083	$2,083 \div 27.778 = \sim 75$
5	2,083	$2,083 \div 27.778 = \sim 75$
6	2,778	$2,778 \div 27.778 = \sim 100$
7	2,951	$2,951 \div 27.778 = \sim 106.25$
8	0	0
9	0	0
10	0	0
11	0	0
12	0	0

Table 13.10
Family Plan
Explosion
Calculations for
Subfamily B

Week	End Item Production Due (CS)	Gross Production Subfamily A (TN)
1	18,750	$18,750 \div 27.778 = \sim 675$
2	6,250	$6,250 \div 27.778 = \sim 225$
3	8,333	$8,333 \div 27.778 = \sim 300$
4	6,250	$6,250 \div 27.778 = \sim 225$
5	6,250	$6,250 \div 27.778 = \sim 225$
6	8,333	$8,333 \div 27.778 = \sim 300$
7	8,854	$8,854 \div 27.778 = \sim 318.74$
8	0	0
9	0	0
10	0	0
11	0	0
12	0	0

The rollup also recalculates the actual end-item forecast percentages and stores these in the family hierarchy record.

Table 13.11
Total Family Gross Production

Week	Total Family Gross Production	Actual Percentage of Forecast from A	Actual Percentage of Forecast from B
1	$234 + 675 = 909$	$234 \div 909 = 25.74\%$	$675 \div 909 = 74.25\%$
2	$75 + 225 = 300$	$75 \div 300 = 25\%$	$225 \div 300 = 75\%$
3	$100 + 300 = 400$	$100 \div 400 = 25\%$	$300 \div 400 = 75\%$
4	$75 + 225 = 300$	$75 \div 300 = 25\%$	$225 \div 300 = 75\%$
5	$75 + 225 = 300$	$75 \div 300 = 25\%$	$225 \div 300 = 75\%$
6	$100 + 300 = 400$	$100 \div 400 = 25\%$	$300 \div 400 = 75\%$
7	$106.25 + 318.74 = \sim 425$	$106.25 \div 425 = 25\%$	$318.74 \div 425 = 75\%$
8	0	0	0
9	0	0	0
10	0	0	0
11	0	0	0
12	0	0	0

In Global Production Maintenance (33.7.3), you would also see that the rollup correspondingly updated the family item's gross production, projected weeks of coverage, and projected quantity on hand.

Operations Plan Example

This example illustrates operations plan calculations for supply sites and production lines. Calculations are shown by planning week.

Source Matrix Explosion

For each week with sales forecasts, Source Matrix Explosion (33.13.8) calculates global forecasts by totaling end-item forecasts from marketing sites.

Table 13.12
Site and Global
Forecasts

Week	Site A Forecasts	Site B Forecasts	Global Forecasts
1	0	0	0
2	0	0	0
3	0	0	0
4	4,000	6,000	10,000
5	7,000	5,000	12,000
6	4,500	6,500	11,000
7	4,500	4,500	9,000
8	5,000	5,000	10,000
9	6,000	5,000	11,000
10	6,000	6,000	12,000
11	8,000	5,000	13,000
12	0	0	0

The explosion uses the item's average weeks-of-coverage factor (2.0) to calculate the global target inventory levels. Therefore, each week's global target inventory equals the sum of the next two weeks of sales forecasts.

Table 13.13
Global Forecasts
and Target
Inventory

Week	Global Forecasts	Global Target Inventory
1	0	0
2	0	10,000 = 0 + 10,000
3	0	22,000 = 10,000 + 12,000
4	10,000	23,000 = 12,000 + 11,000
5	12,000	20,000 = 11,000 + 9,000
6	11,000	19,000 = 9,000 + 10,000
7	9,000	21,000 = 10,000 + 11,000
8	10,000	23,000 = 11,000 + 12,000
9	11,000	25,000 = 12,000 + 13,000
10	12,000	13,000 = 13,000 + 0
11	13,000	0
12	0	0

The explosion calculates global production due as (Sales Forecast + Target Inventory) – Previous Projected Quantity on Hand. For week 1, the

previous projected QOH is 3,000, the ending inventory balance from the previous week.

Week	Sales Forecast	Target Inventory	Projected QOH	Production Due
1	0	0	3,000	0
2	0	10,000	10,000	$7,000 = (0 + 10,000) - 3,000$
3	0	22,000	22,000	$12,000 = (0 + 22,000) - 10,000$
4	10,000	23,000	23,000	$11,000 = (10,000 + 23,000) - 22,000$
5	12,000	20,000	20,000	$9,000 = (12,000 + 20,000) - 23,000$
6	11,000	19,000	19,000	$10,000 = (11,000 + 19,000) - 20,000$
7	9,000	21,000	21,000	$11,000 = (9,000 + 21,000) - 19,000$
8	10,000	23,000	23,000	$12,000 = (10,000 + 23,000) - 21,000$
9	11,000	25,000	25,000	$13,000 = (11,000 + 25,000) - 23,000$
10	12,000	13,000	13,000	0
11	13,000	0	0	0
12	0	0	0	0

Table 13.14
Production Due
Calculations

The explosion initially calculates projected quantity on hand to equal the target inventory level. However, if you change production due, the system recalculates it as:

$$(Previous\ Week's\ Projected\ QOH + Production\ Due) - Sales\ Forecast$$

The explosion initially calculates projected weeks of coverage as the item's average weeks-of-coverage factor. But the system recalculates it when you change production due.

For each week, the system subtracts the forecast for each upcoming week, until it encounters a week for which the on-hand quantity is insufficient to cover the forecast. It then divides the remaining inventory by the sales forecast for the week. Finally, it calculates weeks of coverage by totaling the number of complete weeks and the decimal for the partial week.

In Table 13.15, the projected weeks of coverage for week 1 is 2.3, because 3,000 is a sufficient quantity to cover the forecasts for the next 2.3 weeks.

For 10, projected weeks of coverage is only 1.0. The projected on-hand quantity is exactly enough to cover the sales forecast for 11, and there are no sales forecasts in the remaining weeks.

Table 13.15
Sales Forecasts
and Projected
Quantities on Hand

Week	Sales Forecasts	Projected QOH	Projected Weeks of Coverage
1	0	3,000	2.3
2	0	10,000	2.0
3	0	22,000	2.0
4	10,000	23,000	2.0
5	12,000	20,000	2.0
6	11,000	19,000	2.0
7	9,000	21,000	2.0
8	10,000	23,000	2.0
9	11,000	25,000	2.0
10	12,000	13,000	1.0
11	13,000	0	0.0
12	0	0	0.0

In this example, all production is distributed to one supply site with two production lines, 001 and 002. The site produces 75% of its requirement for the item on line 001 and the remaining 25% on line 002.

Table 13.16
Site and Line
Production Due

Week	Total Site Production Due	Line 001 Production Due (75%)	Line 002 Production Due (25%)
1	0	0	0
2	7,000	5,250	1,750
3	12,000	9,000	3,000
4	11,000	8,250	2,750
5	9,000	6,750	2,250
6	10,000	7,500	2,500
7	11,000	8,250	2,750
8	12,000	9,000	3,000
9	13,000	9,750	3,250
10	0	0	0
11	0	0	0
12	0	0	0

The formula for projected line production hours is $\text{Line Production Due Quantity} \div \text{Hourly Line Production Rate}$. For line 001, the production rate is 375 units per hour. For line 002, it is 125 units per hour.

Table 13.17
Line 001 Projected
Production Hours

Week	Line 001 Projected Production Hours
1	0
2	$14 = 5,250 \div 375$
3	$24 = 9,000 \div 375$
4	$22 = 8,250 \div 375$
5	$18 = 6,750 \div 375$
6	$20 = 7,500 \div 375$
7	$22 = 8,250 \div 375$
8	$24 = 9,000 \div 375$
9	$26 = 9,750 \div 375$
10	0
11	0
12	0

Table 13.18
Line 002 Projected
Production Hours

Week	Line 002 Projected Production Hours
1	0
2	$14 = 1,750 \div 125$
3	$24 = 3,000 \div 125$
4	$22 = 2,750 \div 125$
5	$18 = 2,250 \div 125$
6	$20 = 2,500 \div 125$
7	$22 = 2,750 \div 125$
8	$24 = 3,000 \div 125$
9	$26 = 3,250 \div 125$
10	0
11	0
12	0

The line utilization percentage is the line's production load divided by its capacity. The weekly capacity is 15,000 cases for line 001 (375×40

hours) and 5,000 cases (125 x 40 hours) for line 002. In this example, both lines have a standard 40-hour weekly shift calendar, and there are no scheduled holiday, downtime, or overtime periods.

Table 13.19
Line 001
Utilization
Percentages

Week	Line 001 Utilization Percentages
1	0%
2	35% = $5,250 \div 15,000$
3	60% = $9,000 \div 15,000$
4	55% = $8,250 \div 15,000$
5	45% = $6,750 \div 15,000$
6	50% = $7,500 \div 15,000$
7	55% = $8,250 \div 15,000$
8	60% = $9,000 \div 15,000$
9	65% = $9,750 \div 15,000$
10	0%
11	0%
12	0%

Table 13.20
Line 002
Utilization
Percentages

Week	Line 002 Utilization Percentages
1	0%
2	35% = $1,750 \div 5,000$
3	60% = $3,000 \div 5,000$
4	55% = $2,750 \div 5,000$
5	45% = $2,250 \div 5,000$
6	50% = $2,500 \div 5,000$
7	55% = $2,750 \div 5,000$
8	60% = $3,000 \div 5,000$
9	65% = $3,250 \div 5,000$
10	0%
11	0%
12	0%

SECTION 2

DRP and Other Planning Modules

This section describes the following modules:

Distribution Requirements Planning **141**

Product Line Plan **167**

Resource Plan **173**

Routing Code: 10-15000
Operation: 20
Standard Operation: 1030
Work Center: Machine
Description: INSPEC PER PROC-000
Machines per Op: 1
Overlap Units: 1
Queue Time: 1.0
Wait Time: 0.0
Setup Time: 0.0

CHAPTER 14

Distribution Requirements Planning

Distribution Requirements Planning (DRP) is a planning function designed for companies with multiple sites having interdependencies of supply and demand. This chapter explains how to use the DRP module to create and maintain a distribution requirements plan.

Introduction **142**

Setting Up DRP **143**

Executing DRP **148**

DRP Output **153**

Routing Maintenance (Main Screen)	
Routing Code:	10-15000
Operation:	20
Standard Operation:	1030
Work Center:	INSPECTION, ALL SITES
Machine:	
Description:	INSPEC PER PROX-005
Machines per Op:	1
Overlap Units:	1
Queue Time:	1.0
Wait Time:	0.0
Setup Time:	0.0

Introduction


Distribution requirements planning (DRP) balances supply and demand in a time-phased manner for items transferred between sites. Typically, these sites exist in several databases connected over a network. DRP calculates distribution item requirements, generates intersite requests, and manages shipment schedules and transportation.

In DRP terms, the site supplying items to another site is called a source or supply site. The site receiving the item is called a receiving or demand site.

See “Intersite Requests” on page 153.

Figure 14.1 illustrates the process DRP uses to generate intersite requests at the receiving site, which are then issued as distribution orders and filled at the source site.

Fig. 14.1
Distribution Order
Life Cycle



Setting Up DRP

To use DRP, you must first establish some basic data used in the planning process. Figure 14.2 summarizes the setup steps.




Fig. 14.2
DRP Data Setup
Work Flow

Pur/Mfg Code

DRP only plans items designated as distribution items. Usually, one site supplies these items to another site. To designate a distribution item, set its Pur/Mfg code to D in Item Master Maintenance (1.4.1), Item Planning Maintenance (1.4.7), or Item-Site Planning Maintenance (1.4.17). Item-Site Planning Maintenance lets you define an item as a distribution item at one site and a non-distribution item—that is, a manufactured or purchased item—at another.

See *User Guide Volume 6: Master Files* for details on defining items.

Item Planning Maintenance

User Menu Edit Queue Options Help

Item Number: 09-0035 Description: Quality Pencil

UM: EA

Item Planning Data

Master Sched: yes	Buyer/Planner:	Phantom: no
Plan Orders: yes	Supplier:	Min Ord: 0
Time Fence: 0	PO Site: 10000	Max Ord: 0
MRP Required: yes	Pur/Mfg: D	Ord Mult: 0
Order Policy: POQ	Configuration:	Op Based Yield: no
Order Qty: 0	Mfg LT: 0	Yield%: 100.00%
Batch Qty: 1.0	Pur LT: 0	Run Time: 0.000
Order Period: 7	Inspect: no	Setup Time: 0.000
Safety Stk: 0	Ins LT: 0	EMT Type: NON-EMT
Safety Time: 0	Cum LT: 0	Auto EMT Processing: no
Reorder Point: 0	Run Seq 1:	Network Code: 10000-10001
Rev:	2:	Routing Code:
Issue Policy: yes		BOM/Formula:

Fig. 14.3
Item Planning
Maintenance
(1.4.7)

Source Networks

Source networks are used by DRP in the same way product structures are used by material requirements planning (MRP). MRP explodes product structures for manufactured items and creates planned orders. Similarly, DRP explodes source networks for distribution items and generates intersite requests.

Supply network relationships can represent a simple, single-tiered distribution environment. At the other extreme, the network can represent a complex, multi-tiered environment. This is typical when one or more plants supply product to each other and to regional distribution centers, which, in turn, supply branch warehouses.

A network code defines one or more supply relationships. Each relationship in the network contains a receiving site, a supply site, and a supply percentage. A relationship is a one-way, site-to-site relationship. Set up one for every demand-to-supply site link. You can group multiple site-to-site relationships under the same source network.

Example If material travels from site A to T and from T to A, two relationships are required.

You must assign each distribution item to a single source network. Do this in Item Master Maintenance (1.4.1), Item Planning Maintenance (1.4.7), or Item-Site Planning Maintenance (1.4.17). DRP plans intersite requests the same way for all items assigned to the same source network. Requests for those items are sent to the same supply sites, calculated using the same supply percentage, and request the same transportation mode or specify the same lead time.

Use Network Code Maintenance (12.1.1) to define network codes. Optionally, you can assign the codes to a planner. Then, use Source Network Maintenance (12.1.13) to specify the relationships in the network.

Fig. 14.4
Source Network
Maintenance
(12.1.13)

Optionally specify a transportation code or lead time. If you have two methods of transportation between the same sites, you must set up separate network codes for each.

A demand site can receive supply requirements for one item from multiple supply sites. Specify this in Supply %.

Transportation Management

The methods a company uses to transport items from source to receiving sites—trucks, ships, containers, and so on—are transportation modes. Define transportation modes in Transportation Mode Maintenance (12.5.1). DRP uses the transportation mode's effectivity dates, load lead time, transit lead time, unload lead time, ship days, and receive days to schedule intersite requests.

Fig. 14.5
Transportation
Mode Maintenance
(12.5.1)

Transportation modes can designate available units—for example, how many trucks or rail cars are available—and the capacity for each unit. You must designate a different transportation mode for each type of transportation unit you want DRP to plan. For example, a company-owned fleet of trucks would use a different transportation mode for each type or size of truck.

A transportation network identifies which method or methods are used to move products between a source and receiving site. Define transportation networks in Transportation Network Maintenance (12.5.5) by entering a transportation mode, also called a transportation code or ID, a source site, a receiving site, and effectivity dates. Lead times and available units default from the transport ID. Specify the days when shipping and receiving can be scheduled.

Fig. 14.6
Transportation
Network
Maintenance
(12.5.5)

	Sun	Mon	Tue	Wed	Thu	Fri	Sat
Ship Days[1]:	no	yes	yes	yes	yes	yes	yes
Receive Days[1]:	no	yes	yes	yes	yes	yes	no

When generating and scheduling intersite requests, DRP calculates transportation lead time by adding the load lead time, transit lead time, and unload lead time. The lead times for the transportation network override the source network lead time. Departure and receipt dates are scheduled only on days permitted by the transportation network, unless there is a holiday or fixed shipping schedule to override it.

In determining transportation load profiles, DRP calculates the projected load at departure using intersite requests for traffic between two sites, transportation modes, and item data for weight and volume. Projected capacity is calculated using transportation modes and transportation networks between the same two sites.

Freight Rate Tables

Optionally, use Freight Rate Table Maintenance (12.5.13) to set up freight rate tables. These are for reference purposes only. They cannot be used to calculate freight charges. You can assign a default rate table to a transportation mode in Transportation Mode Maintenance.

Master Scheduling Distribution Items

Items distributed to other sites in the supply chain must be master scheduled differently from other items since they are subject to intersite requests.

Unless you use purchase and sales orders to handle intersite supply and demand, do not enter forecasts for intersite demand, because intersite requests do not consume forecast. For example, a forecast for 100 units and an intersite request for 100 units would add up to a total demand of 200 units.

- When creating shipment forecasts in the Forecast/Master Plan module, enter monthly forecast values as the sum of the gross sales forecast and the net intersite forecast.

Example A site forecast indicates that 1000 units will be sold directly to customers and an additional 400 units will be shipped to other sites. Intersite requests have been received for 150 units in that period. The gross sales forecast is 1000 units while the net intersite forecast is 250 units. For that period, enter a forecast of 1250.

- Enter master scheduled orders for distribution items. Be aware that DRP may consider these as excess supply and generate action messages recommending that you de-expedite or cancel them.

◆ See *User Guide Volume 3: Manufacturing*.

◆ See “Purchase Orders and Sales Orders” on page 163.

Tip
Maintaining the forecast this way can be time-consuming.

Executing DRP

DRP is typically run regularly, often daily. Run DRP only when no activity is underway that could affect source networks, product structures, inventory, demand, or supply. Run DRP-related reports and inquiries immediately after DRP.

DRP Modes

You can run DRP in three operational modes:

- Net Change
- Regenerative
- Selective


You can run DRP for more than one site at a time. Since this may take some time to process, consider using batch mode.

Net Change Distribution Plan

Tip
Set Update MRP Flags in Transportation Network Maintenance to Yes only when you make changes that impact DRP calculations.

Net Change Distribution Plan (12.13.1) recalculates demand only for items with MRP Required set to Yes in the item planning data. If Update MRP Flags in Transportation Network Maintenance (12.5.5) is Yes, the system sets the MRP Required flag for DRP items at that receiving site to Yes. DRP therefore plans for that receiving site the next time it is run in net change mode. The system also sets an item's MRP Required flag to Yes when demand data or item planning parameters change for that item.

Fig. 14.7
Net Change
Distribution Plan
(12.13.1)




Regenerative Distribution Plan

Regenerative Distribution Plan (12.13.2) and Net Change Distribution Plan produce the same results. However, net change often runs more quickly. It looks only at distribution items that have had a change in inventory information, design, forecast, cost, and so on since DRP was last run. Regenerative DRP plans for all items in the site database.

Selective Distribution Plan

Selective Distribution Plan (12.13.3) lets you select the items you want to plan. It is useful for simulations, but use it carefully. It does not always yield the same results as net change or regenerative DRP because it does not implode higher-level requirements.



The screenshot shows a software window titled "Selective Distribution Plan" with a menu bar (User Menu, Edit, Queue, Options, Help) and a toolbar. The main area contains several input fields and checkboxes:

- Item Number: [text box]
- Site: [text box]
- To: [text box]
- To: [text box]
- Master Scheduled Items: ☒ yes
- Non Master Scheduled Items: ☒ yes
- MRP Items: ☒ no
- DRP Items: ☒ yes
- Required Items Only: ☒ yes
- Resolve Low Level Codes: ☒ yes
- Synchronized Calculation: ☒ yes
- Synchronization Code: [text box]
- Buyer Planner: [text box]
- Prod Line: [text box]
- Group: [text box]
- Item Type: [text box]
- Supplier: [text box]
- Pur/Mfg: [text box]
- Output: [text box]
- Batch ID: [text box]

Fig. 14.8
Selective
Distribution Plan
(12.13.3)

Run Selective Distribution Plan in net change mode by setting Required Items Only to Yes. Run it in regenerative mode by setting Required Items Only to No. Plan for small groups of items by specifying combinations of buyer/planner, product line, group, item type, supplier, and Pur/Mfg code.

DRP and MRP

▶ See *User Guide*
Volume 3:
Manufacturing.

To manage the supply, demand, and resources of a supply chain, DRP must be integrated with MRP. The two systems are complementary. MRP balances supply and demand within a site, while DRP balances supply and demand between sites.

MRP considers intersite requests as demand at the source site. Therefore, when to run DRP in relation to MRP depends on where distribution items appear in the product structures for that site.

- For sites that distribute finished products, you usually run DRP before MRP to generate demand for those products at other sites.
- For sites that supply component items to other sites, run MRP first.

If you have DRP items at multiple levels of product structures for a site, you can also run MRP and DRP in combination. MRP and DRP take advantage of the intersite low-level codes. Combined MRP/DRP, a field in both the MRP Control File (23.24) and in the DRP Control File (12.13.24), allows MRP to pass gross requirements to DRP items. DRP creates the intersite request, creating demand at the supply site. The item at the supply site is then planned by MRP.

Running MRP and DRP in combination is especially useful if you use centralized purchasing—common materials are purchased by multiple sites from common suppliers. Lowest-level items (the items highest in your bills) are processed first, regardless of site, and all purchase orders are planned after all site and intersite demand has been calculated.

If you choose to run MRP and DRP separately, MRP creates gross requirements for DRP items, but then does not use DRP to plan the intersite request. MRP simply completes the site or sites where it is run.

A later DRP run explodes the gross requirements for distribution items and creates the intersite requests. These should now be exploded at the supply site using MRP. The only advantage of running the two programs separately is that the processing times are separated into two periods—a possible requirement if there are hardware limitations.

DRP Calculation and Processing

Like MRP, DRP reviews all sources of demand and supply at a given site and plans items in sequence by low-level code. A distribution item's low-level code is based on the product structure attached to the item at the supply site. DRP and MRP calculations use the same algorithms. Calculations are the same when time-phasing supply and demand, netting requirements, planning supply, and reporting exception conditions.

▶ See *User Guide Volume 3: Manufacturing*.

Since source networks are to DRP what product structures are to MRP, the explosion logic is the same. DRP explodes source networks for distribution items, identifying the sites that supply this item and the percentage of the requirement to be satisfied by each, and generates intersite requests rather than planned orders.

To project inventory balances and calculate net requirements, DRP tentatively reschedules intersite requests and plans all activity based on this schedule. It also generates action messages recommending actions a planner should take to execute the plan.

▶ See "DRP Action Messages" on page 163.

Pegging

DRP source-to-requirement pegging lets you associate sources of demand or supply at one site with plans at another. Since sources of demand are exploded based on source networks rather than product structures, pegging is done across sites. Use DRP Detail Inquiry (12.13.16) or DRP Detail Report (12.13.17) to review sources of intersite supply and demand for an item.

- Sources of demand display with the due date, quantity, intersite request number, and receiving site.
- Sources of supply display with the due date, quantity, intersite request number, and source site.

Synchronized MRP/DRP Calculations

If you use Symmetric Multiple Processor (SMP) computers, use the Synchronized Calculation and Synchronization Code fields to run multiple MRP/DRP sessions at the same time. On these machines, you can run one session on each available machine for a given synchronization code against a single database.

Tip
Without SMP computers, these fields have no impact on DRP or MRP processing.

To run synchronized MRP/DRP, use any of the materials or distribution requirements planning programs. Open multiple views of the program. In each view, specify selection criteria for site, item, and so on. Set Synchronized Calculation to Yes and enter the same Synchronization Code for all views. Then start the program in each view.

During synchronized runs, the system creates a master work file listing all records that require planning and then updates the low-level codes. Then each session selects the first available record from the work file, planning the lowest-level items first. When an item is planned, its MRP Required flag is set to No, so it is not replanned by another session. When a session completes planning at the lowest level, it waits until the other sessions are complete at that level. Then all sessions plan the next level up. This continues until all items are planned.

For more efficient processing, start the sessions with identical selection criteria—for example, the same site range—then all sessions select the next available record for planning. This results in the most efficient processing. When any planning level is finished, a session only waits for the other sessions to complete that level before all sessions can start on the next level.

If you start one session for each site, or for distinct site ranges, then when a session completes a level, it must wait for all other sessions to complete planning at that level. For sites with many items at a given level, that creates many more orders, requiring more time to process. Even if one SMP machine is being used by another unrelated process, you could end up with temporarily idle sessions. The advantage of running sessions by distinct ranges is that the audit reports print the planned items in the ranges you entered in each session.

Synchronization codes distinguish a synchronized calculation. All sessions started with the same synchronization code access the same work file of items for replanning. If a session is started with a different synchronization code, it will run without waiting for other sessions running at the same time. This can cause locking problems and double processing. A blank synchronization code is valid.

In some situations, running one session in non-synchronized mode may increase processing efficiency.

Example You have a DRP receiving site that generates demand to two other sites but receives no demand itself. You run the session for the DRP receiving site in non-synchronized mode. That site is planned without waiting for the supply sites, and the two DRP supply sites wait only for the first site to generate the appropriate DRP demand. Once this is created, the two supply site sessions start their runs without waiting for the entire first calculation to complete.

Once again, it would be more efficient to run as three synchronized calculations for the same site range. However, using separate site ranges would make the audit reports simpler to read.

Note Synchronized MRP/DRP does not run on ORACLE databases. PROGRESS allows multiple sessions to select records from a work file and keeps them from attempting to calculate the same item at the same time, but ORACLE does not. Attempting to run synchronized calculation on ORACLE databases may result in double processing and locking conflicts between sessions.

DRP Output

Like MRP, DRP generates planned orders and action messages. Since DRP planned orders represent demands on other sites, they are called *intersite requests*.

At the source site, you can group intersite requests into distribution orders.

Intersite Requests

Intersite requests are to DRP what planned orders are to MRP. To the receiving site, they are like purchase requisitions or supply records. At the source site, they are like sales orders or demand records—external sources of demand that can be master scheduled.

MRP creates the initial demand for DRP-planned items at the receiving site. Running DRP at the receiving site generates intersite demand at the source site at the same time it generates intersite requests for the receiving site.

Intersite requests are visible at both sites. A change to an intersite request at the receiving or source site is automatically reflected in the corresponding request at the other site.

To transfer intersite requests automatically, the source and receiving sites must be connected over the computer network. If they are not, you can transfer intersite requests to the source sites in batch after running DRP at the receiving sites.

Optionally, you can then confirm intersite demand at the source site. The source site translates this demand into distribution orders, which are picked and shipped to the receiving site. These orders are received at the receiving site in the same manner as purchase orders.

Managing Intersite Requests

Create intersite requests at a receiving site manually with Intersite Request Maintenance (12.15.1) or by running DRP. You can also use Intersite Request Maintenance to modify request status, due date, and receiving location at the receiving site. This site determines the quantity ordered and the transportation code for orders from each source site. You can change the transportation code, but not the quantity ordered, at the source site.

Fig. 14.9
Intersite Request
Maintenance
(12.15.1)

The screenshot shows the 'Intersite Request Maintenance' window with a menu bar (User Menu, Edit, Queue, Options, Help) and a toolbar. The main area contains the following fields:

Site:	Requisition:
Item Number:	
Order Date:	Sales/Job:
Due Date:	Location:
Quantity:	Comments:
Status:	
Remarks:	
Shipping Site:	Qty Confirmed:
Qty Ordered:	Qty Received:
Transportation Code:	Qty Shipped:
Ship Date:	Order Number:
Due Date:	In Transit Site:
Comments:	Project:
Remarks:	

Like work orders, intersite requests can have a status of planned, firm planned, exploded, allocated, released, or closed. Requests with a status of planned can be modified or deleted by the system when DRP is run.

Manually changing the status to firm planned or released causes DRP not to change the order due date, ship date, or quantity for that request the next time it is run.

At the source site, use Intersite Demand Confirmation (12.17.1) to confirm all, or portions of, the quantity, due date, ship date, transportation code, and in-transit site for an intersite request. If any part of a request has been confirmed, DRP plans using the quantities and dates confirmed by the source site. If an intersite request has not been confirmed, DRP processes it for the quantities and due dates automatically generated by the system.

To summarize planning at a source site, the intersite demand appears as the Gross Reqs value in the Master Schedule Summary and is treated as independent demand. You can adjust the demand quantity during demand confirmation. The remainder of the process at a source site involves transportation planning, order aggregation, and shipping.

DRP creates intersite requests if there is a requirement at a site that meets the following criteria:

- Item required has a non-blank Order Policy and Plan Orders is Yes in Item Master Maintenance (1.4.1).
- Item's Pur/Mfg code is D.
- A source network exists.
- The system has access to the source sites.

When DRP creates intersite requests, it schedules the shipment date at the source site and the due date at the receiving site. DRP calculates these dates using the lead times defined for the transportation network. If none are defined, the system retrieves the lead times defined for either the transportation code or the source network assigned to it.

Goods in transit are tracked using the product line inventory or product line inventory detail accounts, sub-accounts, and cost centers. In an average costing environment, avoid potential discrepancies in account balances by making the following the same:

- The Inventory account, sub-account, and cost center entered in Product Line Maintenance (1.2.1)
- The Inventory account, sub-account, and cost center entered in Inventory Account Maintenance (1.2.13)

If you have any inventory in transit when you implement MFG/PRO eB, run the utility program `utdsgit.p` to adjust all in-transit orders.

Delete or archive intersite requests for the receiving site as needed using Intersite Request Delete/Archive (12.15.23). For requests at the source site, do this using Closed Intersite Demand Del/Arch (12.17.23).

Managing Database Connections

To execute DRP in the supply site, active database connections must be available. In the demand site, it is possible to run DRP and transfer or import demand records later.

Demand Database

When DRP is executed in the demand database and determines that the source database is unavailable, it writes demand records into an equivalent file in the local database. Transfer these records to the new database in two ways:

- When the connection comes back up, run Intersite Demand Transfer (12.15.9). This takes the records in the local file and moves them to the equivalent file in the other database.

If the intersite requests were modified in the supply database while the connection was down, the transferred requests overwrite the new versions in the supply database. It is assumed the intersite request records in the demand database take precedence.

- Run Intersite Demand Export (12.15.10) in the demand database. This exports the records to a file in a subdirectory of the current directory with the name of the supply database.

When the file is created, use Intersite Demand Import (12.17.10) to import it into the supply database. The default file name is the same as that for Intersite Demand Export.

Intersite Demand Export and Import are useful when there are many demand records or when network connections for large files are unreliable or nonexistent.

Tip
To avoid an error, set up this subdirectory before exporting the transactions.

Supply Database

The export/import programs only transfer information from the demand database to the supply database. The supply database must remain connected to the demand database to confirm or enter distribution orders for the demand database.

When a connection comes back up, run Intersite Demand Validation (12.17.12) from the supply database. This looks at existing intersite demand in the supply database. If changes occurred while the system was down, the program replaces that demand with records from the demand database. It does not look at new demand—only at existing demand records in the supply database.

This process can be slow because the system needs to determine what action to take with each demand record.

Distribution Orders

At a source site, you can process several intersite requests at one time by combining them in a distribution order, the same way purchase requisitions are combined into purchase orders. Distribution orders simplify picking and shipping materials from one site to another.

At the supply site, distribution orders typically follow this life cycle:

- Create distribution orders in Distribution Order Maintenance (12.17.14).
- Print orders with Distribution Order Print (12.17.18).
- Print a picklist with Distribution Order Picklist Print (12.17.19).
- Ship orders with Distribution Order Shipments (12.17.22). Additional shipping features are available when a shipping group exists for the distribution order.

♦ See *User Guide Volume 2: Distribution* for details on shipping.

At the receipt site, distribution order shipments can be received with Distributed Order Receipt (12.15.20). Any comments you add at the time you create the distribution order in Distribution Order Maintenance print on the Distribution Order Report (12.17.16), Distribution Order Print, and Distribution Order Picklist Print.

When inventory is issued and received using distribution orders, it is actually transferred to and from an in-transit inventory site. The in-transit site defaults to the receiving site. This assumes that title is transferred to the receiving site at shipment (FOB destination). The site can be changed to the source site (or another site) using Intersite Demand Confirmation (12.17.1). The in-transit location is the transportation code. For distribution orders, inventory location codes should correspond to transportation codes.

Set the quantity to receive by setting Receive All in Distributed Order Receipt (12.15.20). If Yes, the quantity to receive is equal to the quantity open on each distribution order line—you enter any variations. If No, the quantity to receive is set to zero and you must enter all receipt quantities.

Note For shipments between countries with differing base currencies, the system uses the exchange rate defined in Exchange Rate Maintenance (26.4).

▶ See *User Guide Volume 4A: Financials* for information on multiple currencies.

▶ See *User Guide Volume 9: Manager Functions* for information on CIM load.

Distribution Order Shipment Detail

The Use Shipment Information field in Distributed Order Receipt (12.15.20) controls the shipment detail the system uses for shipment receiving. If Yes, the system uses full shipment detail for the default quantities and item detail being received. If No, it uses only the items and total quantities during receipt. This may be appropriate if you are entering data through CIM load.

Fig. 14.10
Distributed Order Receipt (12.15.20)

Item Numbr	Site	Req Nb	Qty Ordere	Qty Ope	Receipt Qt

Item Number:

Req:

Site:

Loc:

Description:

Lot/Serial:

Qty Open:

UM:

Ref:

Qty To Receive:

Multi Entry:

When Use Shipment Information is Yes, all issue data for the order is loaded. The Qty to Receive is set equal to the Qty Open, and any item

detail such as lot/serial numbers, reference numbers, or locations is preserved and appears in the multi-entry window. You can alter the receipt items, quantities, or item detail if necessary, or accept the entire shipment as the default receipt.

When detailed shipment data is no longer available, set Use Shipping Information to No. This is appropriate if a stocking software is used to receive the shipment and modified data is then CIM loaded. The Qty Ordered displays the shipped quantities, but Qty to Receive is set to zero.

Using CIM load for Distributed Order Receipt, you can receive a number of items for any quantity in a single transaction as long as those items do not have lot/serial, location, or reference detail. When CIM loading multi-lot/serial, location, or reference items, you can only receive a single lot/serial, location, or reference item per receipt transaction. If you attempt to receive the same item number again with unique detail, it overwrites the first receipt record.

When you receive the items, received item quantities and detail are checked against the shipment detail and, where a match exists, in-transit quantities are reduced. For any items that do not match—if you receive less, or use a different lot or serial number—the shipment detail is not decremented. You can see any remaining shipment detail for an order by reentering Distributed Order Receipt and setting Use Shipping Information to Yes. You should resolve these discrepancies and correct any errors using negative quantities.

Distribution Order Workbench

Distribution Order Workbench (12.17.13) lets the source site group intersite requests and issue distribution orders based on the group. The workbench is a combination of the intersite demand and intersite order programs.

The workbench process has three steps:

- You define selection criteria to group outstanding intersite requests.
- The system creates a distribution order to satisfy these requests.
- The system determines which of the requests will be filled on the generated order.

Tip

Use this when attaching an intersite demand to a distribution order is impractical.

Request Grouping

In the first step, specify selection criteria for listing requests, based on source site, ship-to site, transportation mode, ship date, and item number.

Fig. 14.11
Distribution Order
Workbench
(12.17.13)

The screenshot shows the 'Distribution Order Workbench' window with a menu bar (User Menu, Edit, Queue, Options, Help) and a toolbar. The main area contains selection criteria fields:

Shipping Site:	12000	To:	15000
Ship-To:		To:	
Transport ID:		To:	
Ship Date:	/ /	To:	/ /
Item Number:		To:	
Avail Only:	yes		
Allocate:	yes		
Record Limit:	450		
B/O Partials:	yes		

The ship date limits the display to requests with ship dates before the specified date. If Avail Only is Yes, selection stops when inventory is exhausted. If Allocate is Yes, the workbench allocates the inventory selected.

The next frame displays intersite requests matching the selection criteria. Requests are sorted first by ship-to site, then by transport mode, and finally by ship date. Group requests by moving the cursor to a line and pressing Enter.

Fig. 14.12
Distribution Order
Workbench
(12.17.13)

The screenshot shows the 'Distribution Order Workbench' window displaying a list of intersite requests. The table has the following columns: Source, Ship-To, Transport, Ship, Ship Weight UM, Size UM, and Items.

Source	Ship-To	Transport	Ship	Ship Weight UM	Size UM	Items
30000	10000		04/08/94	9,900.0 lb	0.0 CC	2
30000	10000		04/15/94	11,000.0 lb	0.0 CC	2
30000	10000		04/22/94	1,560.0 lb	0.0 CC	2
30000	10000		04/29/94	0.0 lb	0.0 CC	2
30000	10000		05/06/94	0.0	0.0	2
30000	10000		05/13/94	0.0 lb	0.0 CC	2

The system selects all requests up to that line that share the same source site, ship-to site, and transportation mode. To select different requests, change the selection criteria or edit the selections after they are made.

Distribution Order Creation

When you press Go, the system creates a distribution order to satisfy the requests. An order created in the workbench is the same as one created in Distribution Order Maintenance (12.17.14), except that you can further limit automatic selection.

Fig. 14.13
Distribution Order
Workbench
(12.17.13)

Ship Date. The earliest ship date listed on any of the selected requests.

Purchase Order. Used to reference an external purchase order.

Ship Via. Further limits the requests to those that have the shipping method specified. The value is the transport ID used to select the requests.

Target Weight. The system stops selecting requests when the stated target weight or target cubic measure is reached, based on summing order ship weights. The target value defaults from the maximum weight defined for that transport ID.

Target Cube. The system stops selecting requisitions when either this cubic measure or the target weight is reached.

Request Selection

The system selects from the list all requests for an item until available inventory for the item is exhausted, the maximum shipping weight or size are reached, or all requests are filled. Next, it displays all selected requests and shows the total weight and space for the items. You can edit this list, which is used for picking and shipping.

Fig. 14.14
Distribution Order
Workbench
(12.17.13)

Distribution Order Workbench					
User Menu Edit Queue Options Help					
Order Number: 20005		Ship-From: 12000	Ship-To: 15000		
Item Number	Requested UM	Confirmed	Selected	B/O	Ship
44-110	100.0 EA	100.0	74.0	yes	05/29/92

Once you have confirmed them, the requests are closed. The system ships partial requests by back-ordering the difference between the request and confirmation quantities.

The item number is not shown until this point, because it is assumed that any items needed by the transport method selected will be shipped. You can control the kinds of items attached to a distribution order by defining a different transportation mode for each item shipped.

Fig. 14.15
Distribution Order
Workbench
(12.17.13)

Distribution Order Workbench					
User Menu Edit Queue Options Help					
Order Number: 20005		Ship-From: 12000	Ship-To: 15000		
Item Number	Ship Date	Quantity UM	Weight UM	Cube UM	
44-110	03/18/96	74.00 EA	592.0	7,400.0	
			592.0	7,400.0	

Question

Is all information correct?

Yes No Cancel

When the requests are selected, the total is shown, and you are prompted to confirm. Once confirmed, you can edit the order, but automatic selection is not rerun.

Purchase Orders and Sales Orders

You can use purchase orders and sales orders instead of intersite requests and distribution orders. At the receiving site, enter purchase orders or supplier schedules instead of intersite requests. At the source site, enter sales orders or customer schedules instead of distribution orders. DRP still creates intersite requests, but deletes them when it sees purchase orders satisfying the projected requirements.

You should use purchase and sales orders instead of intersite requests and distribution orders if:

- Base currencies differ between sites.
- Taxes need to be calculated and recognized in the general ledger.
- Documentation must be produced for customs.

To use intersite purchase and sales orders, set up procedural controls to ensure that sales orders at source sites mirror purchase orders at receipt sites. Also, enter the inventory site codes for the customer and supplier address codes.

There are two drawbacks to using purchase and sales orders instead of intersite requests and distribution orders:

- There are no in-transit inventory records.
- There is little or no data for transportation planning, which normally uses load information from intersite requests.

DRP Action Messages

DRP generates action messages recommending what actions a planner should take, such as rescheduling, canceling, or releasing intersite requests. Usually, you delete action messages after reviewing them so you can track which messages you have acted on. Use one of these programs:

- DRP Action Message Review/Update (12.13.5)
- Order Action Message Inquiry (12.13.6)
- DRP Action Message Report (12.13.7)
- The action message review functions in the MRP module. Both MRP and DRP action messages display in all of these functions. They are not kept separate.

To delete the messages displayed on the screen, specify Delete All. Delete Single displays each message and prompts you to delete it.

Deleted messages cannot be recovered. However, if you did not take the recommended action, the message displays again next time you run MRP/DRP.

The first screen selects the action messages to review, usually for a specific Buyer/Planner, and displays them for one Item Number at a time, until there are no more messages, or you press End. At the bottom of each screen of messages, you can delete some or all of them.

Table 14.1 details the action messages generated by DRP.

Table 14.1
DRP Action
Messages

Message	Description
Beginning quantity less than zero.	Initial nettable quantity on hand is negative.
Beginning available less than zero.	Quantity on hand less safety stock is negative.
Create intersite request.	An intersite request should be created to satisfy a negative projected on-hand balance. This message is only generated if the Plan Orders flag is set to No, or if a new requirement appears within the time fence.
De-expedite [order type].	A scheduled intersite request is due before it is needed and should be delayed, or demand rescheduled to an earlier date.
Expedite [order type].	A scheduled intersite request is due after it is needed and should be rescheduled to an earlier date, or demand rescheduled to a later date.
Cancel [order type].	A scheduled intersite request is no longer needed and should be deleted.
Release due for [order type].	Specified supply order should be released. For planned orders, these must also be approved. Using the Order Release Horizon field in the MRP Control File, you can specify the number of days prior to the actual release date for this action message to appear. This may be useful to give the planner visibility of orders to be released.
Release past due for [order type].	Specified supply order was not released when it was due. It now needs to be released and expedited, or the demand must be rescheduled for a later date.

Message	Description
Quantity less than minimum [order type].	This indicates that the specified planned supply order was created for a quantity less than the minimum quantity set in the item master. This appears only for MRP planned orders.
Quantity exceeds maximum [order type].	This indicates that the specified planned supply order was created for a quantity greater than the maximum quantity set in the item master. This appears only for MRP planned orders.
Past due [order type].	Specified supply order receipt is past the due date.
Time fence conflict—[order type].	Unsatisfied material requirement inside the planning time fence for the item. MRP will not create planned orders within the time fence. A planner can try to schedule and expedite an order, or try to delay fulfillment of the requirement that created the demand.
Shipment due for [order type].	A shipment for a DRP item is due. Action must be taken at the source site to ensure the order is received on time.
Shipment past due for [order type].	A shipment for a DRP item is past due. The orders that created the requirements for the item must be delayed or else expedited upon arrival of the item.
No source of supply for [order type].	There is not a valid source network for the date a DRP item is required. Either the item or item-site does not reference a source network, or the source network is not effective on that date.
Planned order count exceeds maximum.	An item/site combination generated the maximum number of planned orders. MRP currently cuts off the creation of orders for that item/site combination at 1000. Calculation for other items continues. This prevents runaway calculations caused by, for instance, an incorrect Order Quantity for an item.

Product Line Plan

Each year, after developing the initial business plan and operating budgets, companies forecast shipments, orders, and production for the upcoming year. The Product Line Plan module lets you enter these forecasts as separate plans and review and adjust relationships between them.

Introduction **168**

Creating Product Line Plans **168**

Balancing Product Line Plans **170**

Maintaining Product Line Plans **171**

Routing Code: 10-15000 OPERATION: 20 STANDARD OPERATION: 1030

Description: INSPEC PER PROX-005

Queue Time: 1.0 Wait Time: 0.0 Setup Time: 0.0


Introduction

MFG/PRO eB product line plans are created annually for each product line or family at a site, and are stated in thousands of currency units per calendar month.

A product line is a group of similar items or products classified together for accounting and planning purposes. You define product lines and link them to appropriate GL accounts in Product Line Maintenance (1.2.1), then assign individual items to product lines in Item Master Maintenance (1.4.1).

The product line plans usually form the basis for the master production schedule.

Fig. 15.1
Product Line Plan
Process Flow



Creating Product Line Plans

Create product line plans in Product Line Plan Maintenance (20.1). You can also use the forecast-specific programs provided in this module to forecast shipments, sales orders, production, inventory, and backlog separately. Then use Product Line Plan Maintenance to reconcile differences between the separate forecasts, as needed. These forecast-specific programs also let you track individual plans by entering actual quantities as the year progresses.

Enter all product line forecasts in currency units of 1,000.

Planning Shipments

Use Shipments Plan Maintenance (20.5) to project how much of a product line you expect to ship per month from a given site and the cost of those shipments.

The difference between shipments and costs is the gross margin for that product line. The system automatically calculates monthly gross margin amounts for the product line, then divides the gross margin quantity by the projected shipment quantity for each month to obtain the gross margin percentages.

Planning Sales Orders

Use Orders Plan Maintenance (20.9) to project how many sales orders will be booked each month for a product line at a given site.

Planning Production

Use Production Plan Maintenance (20.13) to project how much of a given product line you will produce each month at a given site.

You can check the production plan against available resources using the Resource Plan module.

♦ See Chapter 16, “Resource Plan,” on page 173.

Planning Inventory

Use Inventory Plan Maintenance (20.17) to project how much of a given product line you will have in inventory each month at a given site.

Enter a beginning inventory level and press Go to have the system automatically calculate monthly inventory forecasts. These forecasts are based on the beginning inventory value plus the production plan forecast minus the cost of shipment forecast for that month.

The inventory value indicates the relationship between production and the cost of goods sold. Production increases inventory value, while the cost of goods sold reduces it.

Some companies plan their inventory levels in terms of the number of times per year it is completely replaced in total value. To calculate

inventory turns, divide the average inventory value for the year by the total cost of sales.

Planning Backlog

Use Backlog Plan Maintenance (20.21) to project the number of open orders for a given product line at a given site in each month.

Enter a beginning backlog value and press Go to have the system automatically calculate monthly backlog forecasts. These are based on the beginning backlog value plus the sales order forecast minus the shipment forecast for that month.

Balancing Product Line Plans

Product Line Plan Maintenance (20.1) displays data from all the separate plans and automatically calculates monthly backlog and inventory forecasts and gross margin percentages.

Shipments, orders, and backlog are defined at revenue values, while cost, production, and inventory are valued at cost.

Balance the overall plan by adjusting the shipment and cost forecasts to obtain the best gross margin figure possible. Then, adjust the sales orders and shipments forecasts to balance income and balance costs against production to balance inventory.

Fig. 15.2
Product Line Plan
Maintenance (20.1)

Product Line Plan Maintenance							
User Menu	Edit	Queue	Options	Help			
Site:	Product Line: 1000		HOME COOLER PRODUC		Year: 1996		
Value in Thousands USD							
	Ship Fcst	Ord Fcst	Backlog	Cost Fcst	Prod Fcst	Inv Fcst	GM %
			35.0			13.0	
January:	234.0	234.0	35.0	230.0	400.0	183.0	1.7
February:	234.0	245.0	46.0	230.0	400.0	353.0	1.7
March:	458.0	435.0	23.0	450.0	400.0	303.0	1.7
April:	479.0	515.0	59.0	450.0	400.0	253.0	6.1
May:	543.0	523.0	39.0	550.0	400.0	103.0	-1.3
June:	543.0	534.0	30.0	550.0	400.0	-47.0	-1.3
July:	543.0	554.0	41.0	470.0	400.0	-117.0	13.4
August:	469.0	453.0	25.0	470.0	400.0	-187.0	-0.2
September:	231.0	231.0	25.0	230.0	400.0	-17.0	0.4
October:	231.0	213.0	7.0	230.0	400.0	153.0	0.4
November:	231.0	213.0	-11.0	230.0	400.0	323.0	0.4
December:	231.0	212.0	-30.0	230.0	400.0	493.0	0.4
Total:	4,427.0	4,362.0		4,320.0	4,800.0		2.4

Maintaining Product Line Plans


Individual shipments, sales orders, production, inventory, and backlog plans created using forecast-specific functions should be updated monthly or quarterly with actual figures. The system automatically subtracts actual amounts from planned amounts to calculate monthly variance and variance percentage values.

Comparing planned amounts and actual results gives you a basis for adjusting production and creating future product line plans.

Introduction 174

Setting Up Resource Plans 174

Calculating Resource Plans 176




Introduction

The Resource Plan module lets you evaluate the feasibility of a production plan or master schedule, providing a basis for adjusting the plan or adding resources.

Resource plans indicate the load on each key resource—that is, the demand the production plan or master schedule places on that resource. Demand is then compared to that resource's capacity.

Fig. 16.1
Resource Plan
Process Flow



Setting Up Resource Plans

To develop a resource plan, first identify key production resources. These are items required to manufacture finished goods that may limit production capacity and cannot be easily increased in the short term—for example, available funds, critical machines, and skilled labor.

You must also define resource bills, or load profiles, specifying the amount of each key resource required to produce one item unit or production plan unit.

Resource Codes

Define key resources in Resource Maintenance (21.1) with a unit of measure such as hours. The first reference for each resource should be the base or average resource capacity, in units, available per day for all workdays. Also define references for:

- Additional resources expected during the year, such as added shifts
- Temporary loss of resources, such as maintenance shutdowns

Include effective dates when these variances will occur.

Each resource can have multiple reference codes and capacities. The total capacity for a resource on a specific date is the cumulative capacity from all of the references in effect on that date.

The system calculates total capacity per month for each key resource using the workdays defined in the standard shop calendar for the site, multiplied by the cumulative resource capacity per day. Non-workdays and holidays are excluded from this calculation.

Reference	Start	End Date	Cap/Day
Base	01/01/98	12/31/98	65.0

Fig. 16.2
Resource
Maintenance (21.1)

Resource Bills

There are two kinds of resource bills—product line resource bills and item resource bills.

Product Line Resource Bills

A product line resource bill indicates the amount of a resource required to produce one unit of the production plan.

Use PL Resource Bill Maintenance (21.5) to define each key resource.

Product Line: 1000 HOME COOLER PRODUC
 Site: 10000
 Resource: 888 Warehouse, Fingoods
 Start Date: 01/01/95
 End Date: 01/01/96
 Quantity Per: 0.3
 Lead Time (Months): 1
 Offset: 1

Fig. 16.3
Product Line
Resource Bill
Maintenance (21.5)

Quantity Per. The amount of this resource required to produce one unit of the production plan, or 1,000 currency units worth of product,

stated in terms of the unit of measure defined in Resource Maintenance.

Lead Time (Months). The number of months during which a resource is required to manufacture this product line at this site.

Offset. The number of months before the start of production that this resource is needed. This may be negative if the resource is not needed until after production is complete.

Item Resource Bills

To evaluate a manufacturing schedule, define item resource bills for each individual item to be evaluated. Indicate the amount of each key resource required to manufacture one unit of that item. Specify this amount as the Resource Quantity Per in Item Resource Bill Maintenance (21.17). Item resource bills are similar to product line resource bills, except that lead time and offset are expressed in days rather than months.

▶ See Chapter 7, “Family-Level Planning,” and Chapter 8, “End-Item Planning,” for more information.

Operations planning functions use item resource bills to verify the feasibility of family and operations plans and calculate resource requirements for family item and end-item production due quantities.

Calculating Resource Plans

The resource load reports and inquiries display resource load subtracted from capacity in one-month increments. A positive remainder indicates undercapacity, while negative remainders indicate overcapacity. If you are over capacity in most or all periods, reduce planned production levels or add more resources for that item or product line.

Resource load can be displayed in graph format with load calculated as percentage of capacity.

Evaluating Product Line Plans

To evaluate a product line plan—that is, to compare the capacity required by the plan with the available capacity for each resource—use PL Resource Load Summary Inquiry or Report (21.9 and 21.10) or PL Resource Load Detail Inquiry or Report (21.11 and 21.12).

The system calculates resource load using the production forecast for each product line and site and the resource quantity per entered for each product line in PL Resource Bill Maintenance. It multiplies the production plan quantity by the quantity per to determine the production load, or the number of resource units required to produce the plan.

Evaluating Manufacturing Schedules

To evaluate a manufacturing schedule—that is, compare the capacity required by the schedule with available resources—use Item Resource Load Summary Inquiry or Report (21.21 and 21.22) or Item Resource Load Detail Inquiry and Report (21.23 and 21.24).

A manufacturing schedule includes all manufacturing orders—repetitive scheduled orders and planned, firm planned, exploded, allocated, and released work orders—that identify a quantity of an item to be produced. These include master schedule work orders, MRP planned orders, repetitive schedules, and open work orders.

The item resource load reports and inquiries are similar to the product line resource load reports and inquiries.

Index

Numerics

12.1.1 144
12.1.13 144
12.5.1 145
12.5.5 146
12.5.13 147
12.13.1 148
12.13.2 149
12.13.3 149
12.13.5 163
12.13.6 163
12.13.7 163
12.13.16 151
12.13.17 151
12.15.1 154
12.15.9 156
12.15.10 156
12.15.20 157, 158
12.15.23 156
12.17.1 155, 158
12.17.10 156
12.17.12 157
12.17.13 159
12.17.14 157
12.17.16 157
12.17.18 157
12.17.19 157
12.17.22 157
12.17.23 156
18.1.22 93
20.5 169
20.9 169
20.13 169
20.17 169
20.21 170
21.1 174
21.5 175
21.9 176

21.10 176
21.11 176
21.12 176
21.17 176
21.21 177
21.22 177
21.23 177
21.24 177
26.4 158
33.3.5 35
33.3.6 36
33.3.13 40
33.3.14 41
33.3.15 41
33.5.1 38
33.5.2 39
33.5.3 39
33.5.5 39
33.5.6 40
33.5.7 40
33.5.13 46
33.5.14 47
33.5.15 47
33.5.17 47
33.5.18 48
33.5.20 50
33.5.21 51
33.5.23 51
33.5.24 52
33.7.1 69
33.7.3 72
33.7.4 75
33.7.5 75
33.7.7 76
33.7.13 78
33.7.14 76
33.7.16 75
33.1.4 28

33.13.1 55
 33.13.3 59
 33.13.4 59
 33.13.5 60
 33.13.6 60
 33.13.8 83
 33.13.13 61
 33.13.14 62
 33.13.15 62
 33.13.17 63
 33.13.18 64
 33.13.19 64
 33.13.21 64
 33.13.22 65
 33.13.23 65
 33.15.1 86
 33.15.6 89
 33.15.9 90
 33.15.10 97
 33.15.11 97
 33.15.12 97
 33.15.15 106
 33.15.17 106
 33.15.19 97
 33.15.20 97
 33.15.21 70, 86
 33.17.1 114
 33.17.3 118
 33.17.6 117
 33.17.13 116
 33.17.14 116
 33.17.16 117
 33.17.17 117
 33.17.19 118
 33.17.20 118
 33.19.1 110
 33.19.2 110
 33.19.4 110
 33.19.5 110
 33.19.7 110
 33.19.13 111
 33.19.14 111
 33.25.1 124
 36.16.5 124
 36.2.1 90
 36.2.5 90

A

action messages
 distribution requirements planning (DRP) 163
 allocations
 production line 47

approval
 operations plan orders 103
 Archive File Reload 124

B

Backlog Plan Maintenance 170
 Balance Target Inventory and MRP 106

C

Calendar Cross-Reference Build 28
 Calendar Cross-Reference Inquiry 28
 calendars
 operations plan 24
 shift
 operations plan 27
 shop
 operations plan 27
 Calender Maintenance 90
 CIM interface
 distribution requirements planning (DRP) 159
 Closed Intersite Demand Del/Arch 156
 control file
 DRP 150
 Operations Plan 29
 conversion
 unit of measure 25
 co-products/by-products
 operations planning 101
 Copy Plan to Simulation 114
 Copy Simulation to Plan 118
 cost management
 family planning 40
 costs
 planning family 40
 Coverage by Date Inquiry 40
 Coverage by Date Maintenance 39
 Coverage by Date Report 40
 Coverage Detail Report 97
 Coverage Summary Report 97

D

delete/archive
 closed intersite demand 156
 intersite requests 156
 operations plan data 123
 Distributed Order Receipt 157, 158
 Distribution Order Maintenance 157
 Distribution Order Picklist Print 157
 Distribution Order Print 157
 Distribution Order Report 157
 Distribution Order Shipments 157
 Distribution Order Workbench 159

- distribution orders 157
 - creating from workbench 161
- distribution requirements planning (DRP) 141–165
 - action messages 163
 - CIM load 159
 - distribution orders 157
 - intersite requests 153
 - master scheduling and 147
 - material requirements planning (MRP) 150
 - operations plan 25, 45
 - pegging 151
 - setup 143
 - source networks 144
 - synchronized calculations 151
 - transportation modes 145
 - transportation networks 146
 - workbench 160
- DRP Action Message Report 163
- DRP Action Message Review/Update 163
- DRP Control File 150
 - operations plan 25
- DRP Detail Inquiry 151
- DRP Detail Report 151
- DRP. *See* distribution requirements planning (DRP)

E

- end-item plans 81–97
 - calculating 83
 - deleting 86
 - maintaining 86
 - setup 44
- enterprise operations plan. *See* operations plan
- enterprise resource planning (ERP) 13
- EOP. *See* operations plan
- Exchange Rate Maintenance
 - distribution orders 158
- explosion
 - family plans 76
 - source matrix 83

F

- Family Hierarchy Change 36
- Family Hierarchy Copy 35
- Family Hierarchy Inquiry 35
- Family Hierarchy Maintenance 34
- Family Hierarchy Report 35
- Family Hierarchy Where-Used Inquiry 35
- Family Item Cost Inquiry 41
- Family Item Cost Maintenance 40
- Family Item Cost Report 41
- Family Plan Explosion 76
 - example 129

- Family Plan Rollup 78
 - example 131
- family plans 67–80
 - calculating end-item demands 76
 - changing 72
 - data collection 54
 - deleting 72
 - example 125–138
 - explosion 76
 - maintaining 70
 - production costs 40
 - projected profit 75
 - rolling up end-item changes 78
 - setup 32
- Family Setup Menu 32
- Forecast Maintenance
 - operations plan use 69
- Forecast/Master Plan module
 - operations plan 14, 82
- freight rates
 - distribution requirements planning (DRP) 147
- Freight Table Maintenance 147

G

- general ledger (GL)
 - operations plan 24
- GL Calendar Inquiry 27
- GL Calendar Report 27
- Global Consolidation 69
 - example 126
- Global Production Inquiry 75
- Global Production Maintenance 72
- Global Production Report 75
- goods in transit
 - accounts and cost centers 155
 - tracking 155

H

- Holiday Maintenance 90
- holidays
 - operations plan 24

I

- Intersite Demand Confirmation 155, 158
- Intersite Demand Export 156
- Intersite Demand Import 156
- Intersite Demand Transfer 156
- Intersite Demand Validation 157
- Intersite Request Delete/Archive 156
- Intersite Request Maintenance 154
- intersite requests 153
 - creating 154

- grouping 160
- managing 154
- Inventory Data Inquiry 64, 110
- Inventory Data Maintenance
 - operations plan 63
- Inventory Data Report 64, 110
- Inventory Plan Maintenance 169
- Item Master Maintenance
 - product line plans 168
- Item Pallet Inquiry 52
- Item Pallet Maintenance 51
- Item Resource Bill Maintenance 176
- Item Resource Load Detail Inquiry 177
- Item Resource Load Summary Inquiry 177
- items
 - planning 81
 - resource bill 176
- Item-Site Consolidation Menu 68
- Item-Site Data Consolidation 60
- Item-Site Data Inquiry 59
- Item-Site Data Maintenance 59
- Item-Site Data Report 60

L

- lead times
 - end-item operations plans 84
 - operations plan 26
- Line Allocation Inquiry 48
- Line Allocation Maintenance 47
- Line Utilization Maintenance 90
- Line Utilization Summary Report 97
- load profiles 174

M

- manager functions
 - operations plan effect 24
- master production scheduling (MPS)
 - distribution requirements planning (DRP) 147
- material requirements planning (MRP)
 - operations plan effect 27, 102
 - synchronized calculations 151
- matrices
 - operations plan 44
- Move Holiday Production Backward field 24
- MRP Control File 27
- multiple databases
 - operations plan 24, 101
- multiple sites
 - operations plan 25

N

- Net Change Distribution Plan 148

- Network Code Maintenance 144
- networks
 - distribution requirements planning (DRP) 144
 - transportation 146

O

- operations plan
 - approval 103
 - data collection 53–65
 - from MFG/PRO eB databases 55
 - from non-MFG/PRO eB databases 59
 - inquiries and reports 61
 - work flow 54
- data flow 14
- delete/archive programs 123
- end-item plans 81–97
- end-item setup 43–52
 - implementation work flow 44
 - line allocations 47
 - source matrices 44
 - target inventory levels 48
- examples 15
- family level setup 31–41
- family-level planning 67–80
- interactions with other MFG/PRO eB modules 22
- multilevel 57
- setup 21–29
- simulation planning 113–119
- system administration 121–124
- target inventory level 37
- transfer of demand 99–108
- Operations Plan Approval 103
- Operations Plan Batch Approval 106
- Operations Plan Control File 29
 - Move Holiday Production Backward field 84
- Operations Plan Detail Report 89
- Operations Plan Explosion 100, 101
- Operations Plan Inquiry 88
- Operations Plan Line Inquiry 90
- Operations Plan Line Maintenance 89
- Operations Plan Maintenance 86
- Operations Plan Resource Inquiry 70, 86
- Operations Plan Summary Report 88
- Order Action Message Inquiry 163
- Orders Plan Maintenance 169

P

- Pallet Inquiry 51
- Pallet Maintenance 50
- pallets
 - operation plan 50
- pegging

- distribution requirements planning (DRP) 151
- Performance Inquiry 111
- Performance Report 111
- PL Resource Bill Maintenance 175
- PL Resource Load Detail Inquiry 176
- PL Resource Load Summary Inquiry 176
- planning
 - distribution requirements 141
 - end-items 81
 - family-level operations plan 67
 - levels 14
 - product lines 167
 - resources 173
- product definition 5
- Product Line Maintenance
 - product line plans 168
- product line plan 167–171
 - resource evaluation 176
- Product Line Plan Maintenance 170
- product lines
 - planning 168
 - resource bill 175
- Production Data Inquiry 65, 110
- Production Data Maintenance 64
- Production Data Report 65
- Production Labor Inquiry 97
- Production Line Update
 - operations plan 26
- production lines
 - allocations 47
- Production Plan Maintenance 169
- Profit Projection Report 75
- Pur/Mfg code
 - DRP items 143
 - operations plan 25
- purchase orders
 - distribution requirements planning (DRP) 163
- purchase requisitions
 - operations plan 104
- purchasing
 - operations plan effect 27

R

- Recalculate Summary Records 124
- Regenerative Distribution Plan 149
- repetitive
 - Primary Line field 26
- Repetitive module
 - operations plan effect 26
- repetitive schedules
 - operations plan 104
- Resource Maintenance 174

- resource plan 173–177
 - calculating 176
 - load profiles 174
 - operations plan use of 26
 - resource bills 174
 - items 176
 - product line 175
 - resource codes 174
- Rollup Percentage Report 76

S

- safety stock
 - operations plan 26
- Sales Data Inquiry 62, 110
- Sales Data Maintenance 61, 77
- Sales Data Report 62, 110
- sales orders
 - distribution requirements planning (DRP) 163
- Seasonal Build Maintenance
 - operations plan 107
- security
 - operations plan 24
- Selective Distribution Plan 149
- Shift Maintenance 93
- shifts
 - operations plan use 27
- shipment detail
 - Distributed Order Receipt 158
- Shipments Plan Maintenance 169
- shop calendar
 - operations plan 27
- Simulation Line Plan Inquiry 117
- Simulation Line Plan Maintenance 117
- Simulation Line Util Maintenance 118
- Simulation Line Util Report 118
- Simulation Plan Inquiry 116
- Simulation Plan Maintenance 116
- Simulation Summary Report 117
- Site Utilization Inquiry 97
- source matrices 44
- Source Matrix Explosion 83
 - example 133
- Source Matrix Inquiry 47
- Source Matrix Maintenance 46
- Source Matrix Report 47
- Source Network Maintenance 144
- source networks 144
- subfamilies 32
- supply chain management 12
- synchronized calculations
 - codes 152
 - limitations 153

- non-synchronized mode 152
- selection criteria 152
- SMP computers 151

T

- target inventory levels
 - end items 48
 - family items 37
- time fence
 - operations plan 26, 103
- Transaction Data Load 55
- transportation
 - modes 145
 - networks 146

- Transportation Mode Maintenance 145
- Transportation Network Maintenance 146

W

- weeks of coverage
 - end items 48
 - family items 37
- Weeks of Coverage Inquiry 39
- Weeks of Coverage Maintenance 38
- Weeks of Coverage Report 39
- work orders
 - operations plan 26, 102, 104
- workbench
 - distribution requirements planning (DRP) 159